

JUNOScope 8.5 Software Release Notes

Release 8.5R4
18 August 2008
Part Number: 530-021971-01
Revision 4

These release notes accompany Release 8.5R4 of the JUNOS software. They describe the key features, documentation, and known problems with the software. The JUNOScope software is a network management application that provides router configuration management, inventory management, software management, operation status, and troubleshooting tools for Juniper Networks J-series, M-series, MX-series, and T-series routing platforms.

You can also find these release notes on the Juniper Networks Technical Publications Web page, which is located at <http://www.juniper.net/>.

Contents

Release 8.5 Features	3
Current Software Release	3
JUNOScope Software Usage Guidelines	3
Install Latest Appropriate Operating System Patches	4
Verify the JUNOScope Image Against Values Published on the Juniper Networks Web Site	4
Upgrading JUNOScope and Password Policies	4
Protecting JUNOScope Data Files	4
Always Use Strong Passwords	5
Change the Default Install Time User from 'admin' to Another Name	5
Disable Access to the Inventory Management System SQL Interface	6
Do Not Enable Debugging on JUNOScope at Installation	6
Use Only HTTPS to Connect from a Browser Client to the JUNOScope Server	6
Use Only SSL to Connect from the JUNOScope Software to Network Devices	6
Do Not Export JUNOScope Data in Clear Text or with the Encryption Key in the Exported Data	7

Disable User Accounts After Login Failure Attempts Within The Time Window Are Exceeded	7
Regularly Back Up the JUNOScope Software Server	7
Installing the JUNOScope Software	7
System Requirements	7
Red Hat Enterprise Linux ES File Package Requirements	8
JUNOScope Client Workstation Requirements	9
RADIUS Server Requirements	9
Syslog Server Requirements	9
Installing the JUNOScope Software	9
Downloading the JUNOScope Software from the Software Download Page	10
Reconfiguring the JUNOScope Software	10
Reinstalling or Upgrading the JUNOScope Software	11
Uninstalling the JUNOScope Software	11
List of Technical Publications	11
Documentation Feedback	18
Requesting Technical Support	19
Revision History	20

Release 8.5 Features

The following features have been added to JUNOScope Release 8.5. For more detailed information, see the appropriate sections of the *JUNOScope Software User Guide*.

- **Audit Partial Configuration**—The JUNOScope software lets you audit a part of the configuration (configlet) running on a device. You can audit differences between part of the running configuration file and a baseline configlet. To audit a partial configuration, select Configuration > Repository > Audit > Audit Partial Configurations. For more information about auditing partial configurations, see the *JUNOScope Software User Guide*.
- **Load Imported Configuration To Multiple Devices**—The JUNOScope software lets you load an imported configuration or part of a configuration (configlet) to multiple routers and perform a bulk configuration update. To load an imported configuration or configlet to multiple routers, select Configuration > Repository > Load Configuration. For more information about loading an imported configuration or configlet to multiple routers, see the *JUNOScope Software User Guide*.
- **Element Management Support for T1600 Internet Router**—The JUNOScope software allows you to configure and manage the T1600 Internet Router using element management tools, such as Looking Glass, Configuration Manager, Software Manager, and Inventory Management. The T1600 router runs the JUNOS Internet software, which offers many advanced routing and security services. For more information about the T1600 router, see the corresponding hardware guide.
- **Element Management Support for the MX480 Ethernet Services Router**—The JUNOScope software allows you to configure and manage the MX480 Ethernet Services Router using element management tools, such as Looking Glass, Configuration Manager, Software Manager, and Inventory Management. The MX480 Ethernet Services router runs the JUNOS Internet software, which offers many advanced routing and security services. For more information about the MX480 Ethernet Services router, see the corresponding hardware guide.

Current Software Release

The current JUNOScope software release is Release 8.5R4. For information about installing the software release, see “Installing the JUNOScope Software” on page 9.

JUNOScope Software Usage Guidelines

- Install Latest Appropriate Operating System Patches on page 4
- Verify the JUNOScope Image Against Values Published on the Juniper Networks Web Site on page 4
- Upgrading JUNOScope and Password Policies on page 4
- Protecting JUNOScope Data Files on page 4
- Always Use Strong Passwords on page 5
- Change the Default Install Time User from ‘admin’ to Another Name on page 5

- Disable Access to the Inventory Management System SQL Interface on page 6
- Do Not Enable Debugging on JUNOScope at Installation on page 6
- Use Only HTTPS to Connect from a Browser Client to the JUNOScope Server on page 6
- Use Only SSL to Connect from the JUNOScope Software to Network Devices on page 6
- Do Not Export JUNOScope Data in Clear Text or with the Encryption Key in the Exported Data on page 7
- Disable User Accounts After Login Failure Attempts Within The Time Window Are Exceeded on page 7
- Regularly Back Up the JUNOScope Software Server on page 7

Install Latest Appropriate Operating System Patches

Apply all appropriate operating system (such as Solaris or Linux) patches to keep the JUNOScope server less vulnerable to discovered exploits. Regularly check for and install updates. For more information, see the *JUNOScope Software User Guide*, “Installing, Reconfiguring, Reinstalling, Upgrading, or Uninstalling the JUNOScope Software” chapter.

Verify the JUNOScope Image Against Values Published on the Juniper Networks Web Site

To ensure the authenticity of the JUNOScope software, compare the hash value of the JUNOScope image with the MD5 or SHA-1 hash values posted on the Juniper Networks Web site at <https://www.juniper.net/support/csc/swdist-encr/swdist-jtk/>. You can validate the JUNOScope image obtained by HTTPS download or from on the CD, for example, `jtk-install-8.5R4-sunos5.sh` for Solaris.

To generate the hash value, use the following command:

```
hostname% openssl dgst -sha1 jtk-install-8.5R4-sunos5.sh
```

Upgrading JUNOScope and Password Policies

When upgrading from JUNOScope 8.1 or earlier, the password policy is not enforced on any existing user accounts. It is recommended that the administrator change the password for existing user accounts in order to comply with the password policy.

Protecting JUNOScope Data Files

During the JUNOScope software installation, you are asked to specify how you want to protect JUNOScope data files. The available options are user, group, and all. Select the User option to specify that only the user who installed the JUNOScope software can read JUNOScope data files.

Always Use Strong Passwords

The initial `admin` account, created at install time, should have an extra-strong password as it cannot be disabled through repeated login failures. The password for the administrator should not match the username, and should not be a word that can be easily guessed.

In general, JUNOScope software passwords must be:

- Easy to remember so that users are not tempted to write them down.
- Contain between 6 and 40 characters, using at least two of the four defined character sets (uppercase, lowercase, numeric, other). The characters in the set "other" are those that can be entered using a single keystroke, or a keyboard character accessed using the Shift key, that does not fall into any of the other three groups.
- Changed periodically.
- Not divulged to anyone.

Weak passwords are:

- Words that might be found in or exist as a permuted form in system files such as `/etc/passwd`.
- The hostname of the system (always a first guess).
- Any word that appears in a dictionary. This includes dictionaries other than English, and words found in works such as Shakespeare, Lewis Carroll, Roget's Thesaurus, and so on. This prohibition includes common words and phrases from sports, sayings, movies, or television shows.
- Permutations of any of the above. For example, a dictionary word with vowels replaced with digits (f00t) or with digits added to the end.
- Any machine-generated password. Algorithms reduce the search space of password-guessing programs and should not be used.

Strong reusable passwords can be:

- Based on letters from a favorite phrase or word, and
- Concatenated with other, unrelated words, along with added digits and punctuation.

Passwords should be changed from time to time. For more information, see the *JUNOScope Software User Guide*, "Installing, Reconfiguring, Reinstalling, Upgrading, or Uninstalling the JUNOScope Software" chapter.

Change the Default Install Time User from 'admin' to Another Name

The JUNOScope administrative default user account name is `admin`. The JUNOScope installation creates this initial JUNOScope administrative user account so the administrator can use it to add other users. Change the default user account name to another name during the installation process. For more information, see the

JUNOScope Software User Guide, “Installing, Reconfiguring, Reinstalling, Upgrading, or Uninstalling the JUNOScope Software” chapter.

Disable Access to the Inventory Management System SQL Interface

During the JUNOScope software installation, you are asked to confirm whether you want to enable access to the Inventory Management System SQL interface. The default is **no**. If you select **no**, the SQL interface cannot be accessed by any other application or host except JUNOScope clients. If you select **yes**, the MySQL database can be accessed by any application with Inventory Management System user credentials.

Do Not Enable Debugging on JUNOScope at Installation

The JUNOScope software installation confirms whether you want to enable debug logging for technical support purposes. The default and recommended setting is **no**. For more information, see the *JUNOScope Software User Guide*, “Installing, Reconfiguring, Reinstalling, Upgrading, or Uninstalling the JUNOScope Software” chapter.

Use Only HTTPS to Connect from a Browser Client to the JUNOScope Server

The JUNOScope software accepts Hypertext Transfer Protocol over Secure Sockets Layer (HTTPS).

The JUNOScope software provides security between the client and the server. MD5 RSA certification is available between the JUNOScope server and the client Web browser. All communication is encrypted between the client Web browser and the JUNOScope server. The JUNOScope software installation creates an X.509 digital certificate to authenticate the HTTPS server. The JUNOScope software administrator can use self-assigned certificates, or have one assigned by a trusted certificate authority.

The JUNOScope software installation prompts for the HTTPS port that the JUNOScope software Web server uses for its transactions. It is recommended that you use the HTTPS port for communication between the JUNOScope Web browsers and the JUNOScope server. For more information, see the *JUNOScope Software User Guide*, “Installing, Reconfiguring, Reinstalling, Upgrading, or Uninstalling the JUNOScope Software” chapter.

Use Only SSL to Connect from the JUNOScope Software to Network Devices

The JUNOScope software uses the SSL JUNOScript access protocol to connect to configured devices on the network. The SSL protocol is preferred because it encrypts security information (such as a password) before transmitting it across the network. For more information about how to use the SSL access protocol to connect to devices, see the *JUNOScope Software User Guide*, “Setting Up Access Methods” chapter.

Do Not Export JUNOScope Data in Clear Text or with the Encryption Key in the Exported Data

When exporting sensitive data in authentication information from the JUNOScope software server, use the **Encrypt sensitive data and provide key at import time** export option. Sensitive data is exported encrypted and the key to decrypt it is not included in the exported data, but is supplied during import. For more information about exporting all data from the JUNOScope server, see the *JUNOScope Software User Guide*, “Importing and Exporting All Settings Data” chapter, or the specific JUNOScope operation chapter export section.

Disable User Accounts After Login Failure Attempts Within The Time Window Are Exceeded

Configure a Global User Authentication Policy to disable user accounts after the login failure attempts within the time window, as defined by the administrator, has been exceeded. Enable the global user authentication policy; it is disabled by default. For more information about creating global authentication policies, see the *JUNOScope Software User Guide*, “Setting Up a Global Authentication Policy” chapter.

Regularly Back Up the JUNOScope Software Server

Perform regular backups of application data stored by JUNOScope to prevent data loss in the event of a disaster. For more information about backing up JUNOScope application data, see the *JUNOScope Software User Guide*, “Backing Up and Restoring the JUNOScope Application Data” chapter.

Installing the JUNOScope Software

This section describes how to install, reconfigure, reinstall, upgrade, and uninstall the JUNOScope software.

Before installing the JUNOScope software, ensure that your network meets the requirements described in the following sections:

- System Requirements on page 7
- Red Hat Enterprise Linux ES File Package Requirements on page 8
- JUNOScope Client Workstation Requirements on page 9
- RADIUS Server Requirements on page 9
- Syslog Server Requirements on page 9
- Installing the JUNOScope Software on page 9
- Reconfiguring the JUNOScope Software on page 10
- Reinstalling or Upgrading the JUNOScope Software on page 11
- Uninstalling the JUNOScope Software on page 11

System Requirements

The JUNOScope software runs on both Sun Solaris servers (see Table 1 on page 8) and Red Hat Linux servers (see Table 2 on page 8). Before you install the JUNOScope

software, ensure that the supported UNIX server workstation on which you install the software meets the following system requirements.

Table 1 on page 8 shows the minimum system requirements for a Sun Solaris server.

Table 1: Sun Solaris Server System Minimum Requirements

System	Minimum Requirement
Operating system	Solaris 5.8 or later
Processor	UltraSPARC III or equivalent
Speed	1.3 GHz or faster
RAM	1 GB
Free disk space	1 GB

Table 2 on page 8 shows the minimum system requirements for a Red Hat Linux server. (See also Table 3 on page 9).

Table 2: Red Hat Linux Server System Minimum Requirements

System	Minimum Requirement
Hardware	Red Hat certified hardware platforms
Operating system	Red Hat Enterprise Linux ES version 3 and 4
Processor	Pentium 4 processor
Speed	2.8 GHz or faster
RAM	1 GB
Free disk space	1 GB

Red Hat Enterprise Linux ES File Package Requirements

If a minimal install of Red Hat Enterprise Linux ES is performed on the server, the JUNOScope software administrator should ensure that the following file packages are installed for the JUNOScope software to run properly (see Table 3 on page 8). All packages should be available in a full install of Red Hat Enterprise Linux ES.

Table 3: Red Hat Enterprise Linux ES File Package Requirements

Version	Required File Packages
----------------	-------------------------------

Table 3: Red Hat Enterprise Linux ES File Package Requirements (continued)

Red Hat Enterprise Linux ES version 3 (Update 6)	krb5-libs-1.2.7-47.i386.rpm XFree86-libs-4.3.0-97.EL.i386.rpm
Red Hat Enterprise Linux ES version 4 (Update 2)	compat-libcom_err-1.0-5.i386.rpm krb5-libs-1.3.4-17.i386.rpm xorg-x11-deprecated-libs-6.8.2-1.EL.13.20.i386.rpm xorg-x11-libs-6.8.2-1.EL.13.20.i386.rpm

To verify that the file package `krb5-libs-1.3.4-17.i386.rpm` is installed, use the following command:

```
hostname% rpm -queryformat "%{NAME}-%{VERSION}-%{RELEASE}-%{ARCH}\n"
           -query krb5-libs
```

You can install each package individually via `rpm`, from the original Red Hat Enterprise Linux ES distribution. To install the file package `xorg-x11-libs-6.8.2-1.EL.13.20.i386.rpm`, use the following command:

```
hostname% rpm -install xorg-x11-libs-6.8.2-1.EL.13.20.i386.rpm
```

JUNOScope Client Workstation Requirements

Ensure that the client workstation from which you connect to the JUNOScope software is running either Microsoft Internet Explorer 6 or Netscape Navigator 6 or later with JavaScript enabled.

RADIUS Server Requirements

Ensure that the RADIUS server complies with *RFC 2865, Remote Authentication Dial-In User Service*.

Syslog Server Requirements

Ensure that the system server (`syslog`) is running and configured to receive JUNOScope system log messages.

Installing the JUNOScope Software

This section describes how to install the JUNOScope Software from the JUNOScope software download page. For more information about installing the JUNOScope software, see the *JUNOScope Software User Guide*.

- Downloading the JUNOScope Software from the Software Download Page on page 10

Downloading the JUNOScope Software from the Software Download Page

To download the JUNOScope software from the Juniper Networks Web site and start the JUNOScope installation, follow these steps:

1. Using a Web browser, go to the following location:

`https://www.juniper.net/junos/swdist/encryption/index.htm`

2. Log in to the Juniper Networks authentication system using the username (generally your e-mail address) and password supplied by a Juniper Networks representative.
3. Download the appropriate JUNOScope software to the server workstation.
4. Start the JUNOScope installation program:

```
hostname% download-directory/jtk-install-8.5R4.X-sunos5-sparc.sh  
install-directory
```

or

```
hostname% download-directory/jtk-install-8.5R4.X-linux2-i386.sh install-directory
```

Replace `download-directory` with the directory into which you downloaded the JUNOScope software from the software download page.

`jtk-install-8.5R4.X-sunos5-sparc.sh` or `jtk-install-8.5R4.X-linux2-i386.sh` is the JUNOScope software file. Where *X* is the current software spin number.

Replace `install-directory` with the directory in which to install the JUNOScope software. If you do not specify an installation directory, the software is installed in the current directory.

Reconfiguring the JUNOScope Software

You can change the following JUNOScope software installation settings without rerunning the installation program. For more information about these settings, see the *JUNOScope Software User Guide*.

- HTTPS and HTTP ports on which the JUNOScope Web server should listen
- Port on which the JUNOScope server listens for control messages
- HTTP port on which the JUNOScope report server should listen
- Java Database Connectivity (JDBC) URL for accessing the JUNOScope database and demo database
- Enable or disable access for SQL interface to Inventory Management System
- Debug logging
- Syslog facility
- Idle session timeout
- Licensed software modules

You cannot change some settings, such as passwords. To change JUNOScope software settings, use the following command:

```
hostname%install-directory/jtk/bin/jtk-setup.sh
```

Reinstalling or Upgrading the JUNOScope Software

The process for reinstalling or upgrading the JUNOScope software is the same as for installing the software. To install the JUNOScope software, see “Downloading the JUNOScope Software from the Software Download Page” on page 10.

To reinstall or upgrade JUNOScope software, you must use the same user ID as the one used for the currently installed software.

Uninstalling the JUNOScope Software

To uninstall the JUNOScope software, follow these steps:

1. Stop the JUNOScope software and database by changing to the directory where you installed the JUNOScope software and typing the following command:

```
hostname% install-directory/jtk/rc.d/jtk stop
```

2. Remove the JUNOScope software by typing the following command:

```
hostname% rm-rf install-directory
```



WARNING: The `rm-rf install-directory` command removes the JUNOScope `install-directory`, including all data.

List of Technical Publications

Table 4 on page 11 lists the software and hardware guides and release notes for Juniper Networks J-series, M-series, MX-series, and T-series routing platforms and describes the contents of each document. Table 5 on page 16 lists the books included in the *Network Operations Guide* series. Table 6 on page 16 lists the manuals and release notes supporting JUNOS software with enhanced services. All documents are available at <http://www.juniper.net/techpubs/>.

Table 7 on page 18 lists additional books on Juniper Networks solutions that you can order through your bookstore. A complete list of such books is available at <http://www.juniper.net/books>.

Table 4: Technical Documentation for Supported Routing Platforms

Book	Description
JUNOS Software for Supported Routing Platforms	

Table 4: Technical Documentation for Supported Routing Platforms (continued)

Book	Description
<i>Access Privilege</i>	Explains how to configure access privileges in user classes by using permission flags and regular expressions. Lists the permission flags along with their associated command-line interface (CLI) operational mode commands and configuration statements.
<i>Class of Service</i>	Provides an overview of the class-of-service (CoS) functions of the JUNOS software and describes how to configure CoS features, including configuring multiple forwarding classes for transmitting packets, defining which packets are placed into each output queue, scheduling the transmission service level for each queue, and managing congestion through the random early detection (RED) algorithm.
<i>CLI User Guide</i>	Describes how to use the JUNOS command-line interface (CLI) to configure, monitor, and manage Juniper Networks routing platforms. This material was formerly covered in the <i>JUNOS System Basics Configuration Guide</i> .
<i>Feature Guide</i>	Provides a detailed explanation and configuration examples for several of the most complex features in the JUNOS software.
<i>High Availability</i>	Provides an overview of hardware and software resources that ensure a high level of continuous routing platform operation and describes how to configure high availability (HA) features such as nonstop active routing (NSR) and graceful Routing Engine switchover (GRES).
<i>MPLS Applications</i>	Provides an overview of traffic engineering concepts and describes how to configure traffic engineering protocols.
<i>Multicast Protocols</i>	Provides an overview of multicast concepts and describes how to configure multicast routing protocols.
<i>Multiplay Solutions</i>	Describes how you can deploy IPTV and voice over IP (VoIP) services in your network.
<i>MX-series Solutions Guide</i>	Describes common configuration scenarios for the Layer 2 features supported on the MX-series routers, including basic bridged VLANs with normalized VLAN tags, aggregated Ethernet links, bridge domains, Multiple Spanning Tree Protocol (MSTP), and integrated routing and bridging (IRB).
<i>Network Interfaces</i>	Provides an overview of the network interface functions of the JUNOS software and describes how to configure the network interfaces on the routing platform.
<i>Network Management</i>	Provides an overview of network management concepts and describes how to configure various network management features, such as SNMP and accounting options.
<i>Policy Framework</i>	Provides an overview of policy concepts and describes how to configure routing policy, firewall filters, and forwarding options.

Table 4: Technical Documentation for Supported Routing Platforms (continued)

Book	Description
<i>Protected System Domain</i>	Provides an overview of the JCS 1200 platform and the concept of Protected System Domains (PSDs). The JCS 1200 platform, which contains up to six redundant pairs of Routing Engines running JUNOS software, is connected to a T320 router or to a T640 or T1600 routing node. To configure a PSD, you assign any number of Flexible PIC concentrators (FPCs) in the T-series routing platform to a pair of Routing Engines on the JCS 1200 platform. Each PSD has the same capabilities and functionality as a physical router, with its own control plane, forwarding plane, and administration.
<i>Routing Protocols</i>	Provides an overview of routing concepts and describes how to configure routing, routing instances, and unicast routing protocols.
<i>Secure Configuration Guide for Common Criteria and JUNOS-FIPS</i>	Provides an overview of secure Common Criteria and JUNOS-FIPS protocols for the JUNOS software and describes how to install and configure secure Common Criteria and JUNOS-FIPS on a routing platform.
<i>Services Interfaces</i>	Provides an overview of the services interfaces functions of the JUNOS software and describes how to configure the services interfaces on the router.
<i>Software Installation and Upgrade Guide</i>	Describes the JUNOS software components and packaging and explains how to initially configure, reinstall, and upgrade the JUNOS system software. This material was formerly covered in the <i>JUNOS System Basics Configuration Guide</i> .
<i>Subscriber Access</i>	Provides an overview of the subscriber access features of the JUNOS software and describes how to configure subscriber access support on the router, including dynamic profiles, class of service, AAA, and access methods.
<i>System Basics</i>	Describes Juniper Networks routing platforms and explains how to configure basic system parameters, supported protocols and software processes, authentication, and a variety of utilities for managing your router on the network.
<i>VPNs</i>	Provides an overview and describes how to configure Layer 2 and Layer 3 virtual private networks (VPNs), virtual private LAN service (VPLS), and Layer 2 circuits. Provides configuration examples.
JUNOS References	
<i>Hierarchy and RFC Reference</i>	Describes the JUNOS configuration mode commands. Provides a hierarchy reference that displays each level of a configuration hierarchy, and includes all possible configuration statements that can be used at that level. This material was formerly covered in the <i>JUNOS System Basics Configuration Guide</i> .
<i>Interfaces Command Reference</i>	Describes the JUNOS software operational mode commands you use to monitor and troubleshoot interfaces.
<i>Routing Protocols and Policies Command Reference</i>	Describes the JUNOS software operational mode commands you use to monitor and troubleshoot routing policies and protocols, including firewall filters.

Table 4: Technical Documentation for Supported Routing Platforms (continued)

Book	Description
<i>System Basics and Services Command Reference</i>	Describes the JUNOS software operational mode commands you use to monitor and troubleshoot system basics, including commands for real-time monitoring and route (or path) tracing, system software management, and chassis management. Also describes commands for monitoring and troubleshooting services such as class of service (CoS), IP Security (IPsec), stateful firewalls, flow collection, and flow monitoring.
<i>System Log Messages Reference</i>	Describes how to access and interpret system log messages generated by JUNOS software modules and provides a reference page for each message.
J-Web User Guide	
<i>J-Web Interface User Guide</i>	Describes how to use the J-Web graphical user interface (GUI) to configure, monitor, and manage Juniper Networks routing platforms.
JUNOS API and Scripting Documentation	
<i>JUNOScript API Guide</i>	Describes how to use the JUNOScript application programming interface (API) to monitor and configure Juniper Networks routing platforms.
<i>JUNOS XML API Configuration Reference</i>	Provides reference pages for the configuration tag elements in the JUNOS XML API.
<i>JUNOS XML API Operational Reference</i>	Provides reference pages for the operational tag elements in the JUNOS XML API.
<i>NETCONF API Guide</i>	Describes how to use the NETCONF API to monitor and configure Juniper Networks routing platforms.
<i>JUNOS Configuration and Diagnostic Automation Guide</i>	Describes how to use the commit script and self-diagnosis features of the JUNOS software. This guide explains how to enforce custom configuration rules defined in scripts, how to use commit script macros to provide simplified aliases for frequently used configuration statements, and how to configure diagnostic event policies.
Hardware Documentation	
<i>Hardware Guide</i>	Describes how to install, maintain, and troubleshoot routing platforms and components. Each platform has its own hardware guide.
<i>PIC Guide</i>	Describes the routing platform's Physical Interface Cards (PICs). Each platform has its own PIC guide.
<i>DPC Guide</i>	Describes the Dense Port Concentrators (DPCs) for all MX-series routers.
JUNOScope Documentation	
<i>JUNOScope Software User Guide</i>	Describes the JUNOScope software graphical user interface (GUI), how to install and administer the software, and how to use the software to manage routing platform configuration files and monitor routing platform operations.

Table 4: Technical Documentation for Supported Routing Platforms (continued)

Book	Description
Advanced Insight Solutions (AIS) Documentation	
<i>Advanced Insight Solutions Guide</i>	Describes the Advanced Insight Manager (AIM) application, which provides a gateway between JUNOS devices and Juniper Support Systems (JSS) for case management and intelligence updates. Explains how to run AI scripts on Juniper Networks devices.
J-series Routing Platform Documentation	
<i>Getting Started Guide</i>	Provides an overview, basic instructions, and specifications for J-series routing platforms. The guide explains how to prepare your site for installation, unpack and install the router and its components, install licenses, and establish basic connectivity. Use the <i>Getting Started Guide</i> for your router model.
<i>Basic LAN and WAN Access Configuration Guide</i>	Explains how to configure the interfaces on J-series Services Routers for basic IP routing with standard routing protocols, ISDN backup, and digital subscriber line (DSL) connections.
<i>Advanced WAN Access Configuration Guide</i>	Explains how to configure J-series Services Routers in virtual private networks (VPNs) and multicast networks, configure data link switching (DLSw) services, and apply routing techniques such as policies, stateless and stateful firewall filters, IP Security (IPsec) tunnels, and class-of-service (CoS) classification for safer, more efficient routing.
<i>Administration Guide</i>	Shows how to manage users and operations, monitor network performance, upgrade software, and diagnose common problems on J-series Services Routers.
Release Notes	
<i>JUNOS Release Notes</i>	Summarize new features and known problems for a particular software release, provide corrections and updates to published JUNOS, JUNOScript, and NETCONF manuals, provide information that might have been omitted from the manuals, and describe upgrade and downgrade procedures.
<i>Hardware Release Notes</i>	Describe the available documentation for the routing platform and summarize known problems with the hardware and accompanying software. Each platform has its own release notes.
<i>JUNOScope Release Notes</i>	Contain corrections and updates to the published JUNOScope manual, provide information that might have been omitted from the manual, and describe upgrade and downgrade procedures.
<i>AIS Release Notes</i>	Summarize AIS new features and guidelines, identify known and resolved problems, provide information that might have been omitted from the manuals, and provide initial setup, upgrade, and downgrade procedures.
<i>AIS AI-Scripts Release Notes</i>	Summarize AI-Scripts new features, identify known and resolved problems, provide information that might have been omitted from the manuals, and provide instructions for automatic and manual installation, including deleting and rolling back.

Table 4: Technical Documentation for Supported Routing Platforms (continued)

Book	Description
<i>J-series Services Router Release Notes</i>	Briefly describe Services Router features, identify known hardware problems, and provide upgrade and downgrade instructions.

Table 5: JUNOS Software Network Operations Guides

Book	Description
<i>Baseline</i>	Describes the most basic tasks for running a network using Juniper Networks products. Tasks include upgrading and reinstalling JUNOS software, gathering basic system management information, verifying your network topology, and searching log messages.
<i>Interfaces</i>	Describes tasks for monitoring interfaces. Tasks include using loopback testing and locating alarms.
<i>MPLS</i>	Describes tasks for configuring, monitoring, and troubleshooting an example MPLS network. Tasks include verifying the correct configuration of the MPLS and RSVP protocols, displaying the status and statistics of MPLS running on all routing platforms in the network, and using the layered MPLS troubleshooting model to investigate problems with an MPLS network.
<i>MPLS Log Reference</i>	Describes MPLS status and error messages that appear in the output of the <code>show mpls lsp extensive</code> command. The guide also describes how and when to configure Constrained Shortest Path First (CSPF) and RSVP trace options, and how to examine a CSPF or RSVP failure in a sample network.
<i>MPLS Fast Reroute</i>	Describes operational information helpful in monitoring and troubleshooting an MPLS network configured with fast reroute (FRR) and load balancing.
<i>Hardware</i>	Describes tasks for monitoring M-series and T-series routing platforms.

To configure and operate a J-series Services Router or SRX-series services gateway running JUNOS software with enhanced services, you must also use the configuration statements and operational mode commands documented in JUNOS configuration guides and command references. To configure and operate a WX Integrated Services Module, you must also use WX documentation.

Table 6: JUNOS Software with Enhanced Services Documentation

Book	Description
All Platforms	
<i>JUNOS Software Interfaces and Routing Configuration Guide</i>	Explains how to configure J-series and SRX-series interfaces for basic IP routing with standard routing protocols, ISDN service, firewall filters (access control lists), and class-of-service (CoS) traffic classification.

Table 6: JUNOS Software with Enhanced Services Documentation (continued)

Book	Description
<i>JUNOS Software Security Configuration Guide</i>	Explains how to configure and manage security services such as stateful firewall policies, IP Security (IPsec) virtual private networks (VPNs), firewall screens, Network Address Translation (NAT), Public Key Cryptography, and Application Layer Gateways (ALGs).
<i>JUNOS Software Administration Guide</i>	Shows how to monitor J-series and SRX-series devices and routing operations, firewall and security services, system alarms and events, and network performance. This guide also shows how to administer user authentication and access, upgrade software, and diagnose common problems.
<i>JUNOS Software CLI Reference</i>	Provides the complete JUNOS software with enhanced services configuration hierarchy and describes the configuration statements and operational mode commands not documented in the standard JUNOS manuals.
J-series Only	
<i>JUNOS Software with Enhanced Services Design and Implementation Guide</i>	Provides guidelines and examples for designing and implementing IPsec VPNs, firewalls, and routing on J-series Services Routers running JUNOS software with enhanced services.
<i>JUNOS Software with Enhanced Services Quick Start</i>	Explains how to quickly set up a J-series Services Router. This document contains router declarations of conformity.
<i>JUNOS Software with Enhanced Services J-series Services Router Hardware Guide</i>	Provides an overview, basic instructions, and specifications for J-series Services Routers. This guide explains how to prepare a site, unpack and install the router, replace router hardware, and establish basic router connectivity. This guide contains hardware descriptions and specifications.
<i>JUNOS Software with Enhanced Services Migration Guide</i>	Provides instructions for migrating an SSG device running ScreenOS software or a J-series Services Router running the JUNOS software to JUNOS software with enhanced services.
<i>WXC Integrated Services Module Installation and Configuration Guide</i>	Explains how to install and initially configure a WXC Integrated Services Module in a J-series Services Router for application acceleration.
<i>JUNOS Software with Enhanced Services Release Notes</i>	Summarizes new features and known problems for a particular release of JUNOS software with enhanced services on J-series Services Routers, including J-Web interface features and problems. The release notes also contain corrections and updates to the manuals and software upgrade and downgrade instructions for JUNOS software with enhanced services.
SRX-series Only	

Table 6: JUNOS Software with Enhanced Services Documentation (continued)

Book	Description
<i>JUNOS Software for SRX-series Services Gateway Release Notes</i>	Summarizes new features and known problems for a particular release of JUNOS software with enhanced services on SRX-series services gateways, including J-Web interface features and problems. The release notes also contain corrections and updates to the manuals and software upgrade and downgrade instructions for JUNOS software with enhanced services.

Table 7: Additional Books Available Through <http://www.juniper.net/books>

Book	Description
<i>Interdomain Multicast Routing</i>	Provides background and in-depth analysis of multicast routing using Protocol Independent Multicast sparse mode (PIM SM) and Multicast Source Discovery Protocol (MSDP); details any-source and source-specific multicast delivery models; explores multiprotocol BGP (MBGP) and multicast IS-IS; explains Internet Gateway Management Protocol (IGMP) versions 1, 2, and 3; lists packet formats for IGMP, PIM, and MSDP; and provides a complete glossary of multicast terms.
<i>JUNOS Cookbook</i>	Provides detailed examples of common JUNOS software configuration tasks, such as basic router configuration and file management, security and access control, logging, routing policy, firewalls, routing protocols, MPLS, and VPNs.
<i>MPLS-Enabled Applications</i>	Provides an overview of Multiprotocol Label Switching (MPLS) applications (such as Layer 3 virtual private networks [VPNs], Layer 2 VPNs, virtual private LAN service [VPLS], and pseudowires), explains how to apply MPLS, examines the scaling requirements of equipment at different points in the network, and covers the following topics: point-to-multipoint label switched paths (LSPs), DiffServ-aware traffic engineering, class of service, interdomain traffic engineering, path computation, route target filtering, multicast support for Layer 3 VPNs, and management and troubleshooting of MPLS networks.
<i>OSPF and IS-IS: Choosing an IGP for Large-Scale Networks</i>	Explores the full range of characteristics and capabilities for the two major link-state routing protocols: Open Shortest Path First (OSPF) and IS-IS. Explains architecture, packet types, and addressing; demonstrates how to improve scalability; shows how to design large-scale networks for maximum security and reliability; details protocol extensions for MPLS-based traffic engineering, IPv6, and multitopology routing; and covers troubleshooting for OSPF and IS-IS networks.
<i>Routing Policy and Protocols for Multivendor IP Networks</i>	Provides a brief history of the Internet, explains IP addressing and routing (Routing Information Protocol [RIP], OSPF, IS-IS, and Border Gateway Protocol [BGP]), explores ISP peering and routing policies, and displays configurations for both Juniper Networks and other vendors' routers.
<i>The Complete IS-IS Protocol</i>	Provides the insight and practical solutions necessary to understand the IS-IS protocol and how it works by using a multivendor, real-world approach.

Documentation Feedback

We encourage you to provide feedback, comments, and suggestions so that we can improve the documentation. You can send your comments to techpubs-comments@juniper.net, or fill out the documentation feedback form at

<http://www.juniper.net/techpubs/docbug/docbugreport.html>. If you are using e-mail, be sure to include the following information with your comments:

- Document name
- Document part number
- Page number
- Software release version

Requesting Technical Support

Technical product support is available through the Juniper Networks Technical Assistance Center (JTAC). If you are a customer with an active J-Care or JNASC support contract, or are covered under warranty, and need postsales technical support, you can access our tools and resources online or open a case with JTAC.

- JTAC policies—For a complete understanding of our JTAC procedures and policies, review the JTAC User Guide located at <http://www.juniper.net/customers/support/downloads/710059.pdf>.
- Product warranties—For product warranty information, visit <http://www.juniper.net/support/warranty/>.
- JTAC Hours of Operation —The JTAC centers have resources available 24 hours a day, 7 days a week, 365 days a year.

Self-Help Online Tools and Resources

For quick and easy problem resolution, Juniper Networks has designed an online self-service portal called the Customer Support Center (CSC) that provides you with the following features:

- Find CSC offerings: <http://www.juniper.net/customers/support/>
- Search for known bugs: <http://www2.juniper.net/kb/>
- Find product documentation: <http://www.juniper.net/techpubs/>
- Find solutions and answer questions using our Knowledge Base: <http://kb.juniper.net/>
- Download the latest versions of software and review release notes: <http://www.juniper.net/customers/csc/software/>
- Search technical bulletins for relevant hardware and software notifications: <https://www.juniper.net/alerts/>
- Join and participate in the Juniper Networks Community Forum: <http://www.juniper.net/company/communities/>
- Open a case online in the CSC Case Manager: <http://www.juniper.net/cm/>

To verify service entitlement by product serial number, use our Serial Number Entitlement (SNE) Tool located at <https://tools.juniper.net/SerialNumberEntitlementSearch/>.

Opening a Case with JTAC

You can open a case with JTAC on the Web or by telephone.

- Use the Case Manager tool in the CSC at <http://www.juniper.net/cm/> .
- Call 1-888-314-JTAC (1-888-314-5822 toll-free in the USA, Canada, and Mexico).

For international or direct-dial options in countries without toll-free numbers, visit us at <http://www.juniper.net/support/requesting-support.html>.

Revision History

18 August 2008—Revision 4, JUNOScope Release 8.5R4

25 April 2008—Revision 3, JUNOScope Release 8.5R3

12 February 2008—Revision 2, JUNOScope Release 8.5R2

16 November 2007—Revision 1, JUNOScope Release 8.5R1

Copyright © 2008, Juniper Networks, Inc. All rights reserved.

Juniper Networks, the Juniper Networks logo, JUNOS, NetScreen, and ScreenOS are registered trademarks of Juniper Networks, Inc. in the United States and other countries. JUNOSe is a trademark of Juniper Networks, Inc. All other trademarks, service marks, registered trademarks, or registered service marks are the property of their respective owners.

Juniper Networks assumes no responsibility for any inaccuracies in this document. Juniper Networks reserves the right to change, modify, transfer, or otherwise revise this publication without notice.

Products made or sold by Juniper Networks or components thereof might be covered by one or more of the following patents that are owned by or licensed to Juniper Networks: U.S. Patent Nos. 5,473,599, 5,905,725, 5,909,440, 6,192,051, 6,333,650, 6,359,479, 6,406,312, 6,429,706, 6,459,579, 6,493,347, 6,538,518, 6,538,899, 6,552,918, 6,567,902, 6,578,186, and 6,590,785.