

TECHNICAL NOTE

MAPPING PACKETEER® APPLICATIONS INTO STRM

OCTOBER 2009

Packeteer devices collect, aggregate, and store network performance data. Once you configure an external flow source for Packeteer, you can send flow information from a Packeteer device to STRM. This allows STRM to:

- Support packeteer FDR records.
- Classify, store, display, report, and apply NBAD to Packeteer data.
- Map standard Packeteer supported applications.
- Support any custom applications.



Note: *This Technical Note applies to systems running STRM 2009.1 and above.*

When you create a new class ID in your Packeteer device, you must map this ID to a STRM application ID. This allows STRM to process the new class ID as a STRM application ID. This document provides procedures for mapping a Packeteer class ID to a STRM application ID.



Note: *For more information on STRM application IDs, see the STRM Application Configuration Guide.*

To map a Packeteer class ID to a STRM application ID:

Step 1 Create the new class ID in the Packeteer device.

For more information on creating a new class ID, see your Packeteer documentation.

Step 2 Log in to STRM, as root.

Step 3 Open the following file:

```
/opt/qradar/conf/packeteer.conf
```

Step 4 At the end of the file, add a line for each new mapping you wish to create in the following format:

```
<class ID>,<application ID>
```

Where:

<class ID> is the Packeteer class ID.

<application ID> is the associated STRM application ID.

Step 5 Save and exit the file.

Step 6 Log in to the STRM interface.

https://<IP Address>

Where <IP Address> is the IP address of the STRM system.

Username: **admin**

Password: <root password>

Where <root password> is the password assigned to STRM during the installation process.

Step 7 Click the **Admin** tab.

The Admin interface appears.

Step 8 In the navigation menu, click **System Configuration**.

The System Configuration panel appears.

Step 9 Click the **System and License Management** icon.

The System and License Management window appears.

Step 10 Select the system you want to restart.

Step 11 From the Actions menu, select **Restart System**.

STRM restarts.

Copyright Notice

Copyright © 2008 Juniper Networks, Inc. All rights reserved. Juniper Networks and the Juniper Networks logo are registered trademarks of Juniper Networks Inc. in the United States and other countries. All other trademarks, service marks, registered trademarks, or registered service marks in this document are the property of Juniper Networks or their respective owners. All specifications are subject to change without notice. Juniper Networks assumes no responsibility for any inaccuracies in this document or for any obligation to update information in this document. Juniper Networks reserves the right to change, modify, transfer, or otherwise revise this publication without notice.

Published: 2009-10-12