



**Unified Access Control**

## **Client Side Changes Guide**

**Release 3.0**  
*March 2009*

**Juniper Networks, Inc.**  
1194 North Mathilda Avenue  
Sunnyvale, CA 94089  
USA  
408-745-2000  
**[www.juniper.net](http://www.juniper.net)**

Part Number: 530-029880-01

## Copyright Notice

This product includes the Envoy SNMP Engine, developed by Epilogue Technology, an Integrated Systems Company. Copyright © 1986-1997, Epilogue Technology Corporation. All rights reserved. This program and its documentation were developed at private expense, and no part of them is in the public domain.

This product includes memory allocation software developed by Mark Moraes, copyright © 1988, 1989, 1993, University of Toronto.

This product includes FreeBSD software developed by the University of California, Berkeley, and its contributors. All of the documentation and software included in the 4.4BSD and 4.4BSD-Lite Releases is copyrighted by the Regents of the University of California. Copyright © 1979, 1980, 1983, 1986, 1988, 1989, 1991, 1992, 1993, 1994. The Regents of the University of California. All rights reserved.

GateD software copyright © 1995, the Regents of the University. All rights reserved. Gate Daemon was originated and developed through release 3.0 by Cornell University and its collaborators. Gated is based on Kirton's EGP, UC Berkeley's routing daemon (routed), and DCN's HELLO routing protocol. Development of Gated has been supported in part by the National Science Foundation. Portions of the GateD software copyright © 1988, Regents of the University of California. All rights reserved. Portions of the GateD software copyright © 1991, D. L. S. Associates.

This product includes software developed by Maker Communications, Inc., copyright © 1996, 1997, Maker Communications, Inc.

Products made or sold by Juniper Networks or components thereof might be covered by one or more of the following patents that are owned by or licensed to Juniper Networks: U.S. Patent Nos. 5,473,599, 5,905,725, 5,909,440, 6,192,051, 6,333,650, 6,359,479, 6,406,312, 6,429,706, 6,459,579, 6,493,347, 6,538,518, 6,538,899, 6,552,918, 6,567,902, 6,578,186, and 6,590,785.

Juniper Networks, the Juniper Networks logo, NetScreen, and ScreenOS are registered trademarks of Juniper Networks, Inc. in the United States and other countries. JUNOS and JUNOSE are trademarks of Juniper Networks, Inc. All other trademarks, service marks, registered trademarks, or registered service marks are the property of their respective owners.

Copyright 2009 Juniper Networks, Inc. All rights reserved.

## FCC Statement

The following information is for FCC compliance of Class A devices: This equipment has been tested and found to comply with the limits for Class A digital device, pursuant to part 15 of the FCC rules. These limits are designed to provide reasonable protection against harmful interference when the equipment is operated in a commercial environment. The equipment generates, uses, and can radiate radio-frequency energy and, if not installed and used in accordance with the instruction manual, may cause harmful interference to radio communications. Operation of this equipment in a residential area is likely to cause harmful interference, in which case users will be required to correct the interference at their own expense.

The following information is for FCC compliance of Class B devices: The equipment described in this manual generates and may radiate radio-frequency energy. If it is not installed in accordance with the instruction manual, it may cause interference with radio and television reception. This equipment has been tested and found to comply with the limits for a Class B digital device in accordance with the specifications in part 15 of the FCC rules. These specifications are designed to provide reasonable protection against such interference in a residential installation. However, there is no guarantee that interference will not occur in a particular installation.

If this equipment does cause harmful interference to radio or television reception, which can be determined by turning the equipment off and on, the user is encouraged to try to correct the interference by one or more of the following measures:

- Reorient or relocate the receiving antenna.
- Increase the separation between the equipment and receiver.
- Consult the dealer or an experienced radio/TV technician for help.
- Connect the equipment to an outlet on a circuit different from that to which the receiver is connected.

**Caution:** Changes or modifications to this product could void the user's warranty and authority to operate this device and may result in the equipment no longer complying with FCC requirements for Class A or Class B digital devices. In that event, your right to use the equipment may be limited by FCC regulations, and you may be required to correct any interference to radio or television communications at your own expense.

## U.S. Government Rights

Commercial software and commercial software documentation: This documentation is commercial computer software documentation and the products (whether hardware or software) covered by this documentation are or contain commercial computer software. Government users are subject to the Juniper Networks, Inc. standard end user license agreement and any applicable provisions of the FAR and its supplements. No further rights are granted.

Products (whether hardware or software) covered by, and information contained in, this documentation are controlled by U.S. Export Control laws and may be subject to the export or import laws in other countries. Nuclear, missile, chemical, biological weapons end uses or end users, whether direct or indirect, are strictly prohibited. Export or re-export to countries subject to U.S. embargo or to entities identified on US export exclusion lists, including, but not limited to, the denied persons and specially designated national lists, is strictly prohibited.

## Disclaimer

THE SPECIFICATIONS AND INFORMATION REGARDING THE PRODUCTS IN THIS MANUAL ARE SUBJECT TO CHANGE WITHOUT NOTICE. ALL STATEMENTS, INFORMATION AND RECOMMENDATIONS IN THIS MANUAL ARE BELIEVED TO BE ACCURATE BUT ARE PRESENTED WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED.

THE SOFTWARE LICENSE AND LIMITED WARRANTY FOR THE ACCOMPANYING PRODUCT ARE SET FORTH IN THE INFORMATION PACKET THAT SHIPPED WITH THE PRODUCT AND ARE INCORPORATED HEREIN BY REFERENCE. IF YOU ARE UNABLE TO LOCATE THE SOFTWARE LICENSE OR LIMITED WARRANTY, CONTACT YOUR JUNIPER NETWORKS REPRESENTATIVE FOR A COPY.

## End User License Agreement

**READ THIS END USER LICENSE AGREEMENT ("AGREEMENT") BEFORE DOWNLOADING, INSTALLING, OR USING THE SOFTWARE.** BY DOWNLOADING, INSTALLING, OR USING THE SOFTWARE OR OTHERWISE EXPRESSING YOUR AGREEMENT TO THE TERMS CONTAINED HEREIN, YOU (AS CUSTOMER OR IF YOU ARE NOT THE CUSTOMER, AS A REPRESENTATIVE/AGENT AUTHORIZED TO BIND THE CUSTOMER) CONSENT TO BE BOUND BY THIS AGREEMENT. IF YOU DO NOT OR CANNOT AGREE TO THE TERMS CONTAINED HEREIN, THEN (A) DO NOT DOWNLOAD, INSTALL, OR USE THE SOFTWARE, AND (B) YOU MAY CONTACT JUNIPER NETWORKS REGARDING LICENSE TERMS.

1. **The Parties.** The parties to this Agreement are Juniper Networks, Inc. and its subsidiaries (collectively "Juniper"), and the person or organization that originally purchased from Juniper or an authorized Juniper reseller the applicable license(s) for use of the Software ("Customer") (collectively, the "Parties").
2. **The Software.** In this Agreement, "Software" means the program modules and features of the Juniper or Juniper-supplied software, and updates and releases of such software, for which Customer has paid the applicable license or support fees to Juniper or an authorized Juniper reseller. "Embedded Software" means Software which Juniper has embedded in the Juniper equipment.
3. **License Grant.** Subject to payment of the applicable fees and the limitations and restrictions set forth herein, Juniper grants to Customer a non-exclusive and non-transferable license, without right to sublicense, to use the Software, in executable form only, subject to the following use restrictions:
  - a. Customer shall use the Embedded Software solely as embedded in, and for execution on, Juniper equipment originally purchased by Customer from Juniper or an authorized Juniper reseller.
  - b. Customer shall use the Software on a single hardware chassis having a single processing unit, or as many chassis or processing units for which Customer has paid the applicable license fees; provided, however, with respect to the Steel-Belted Radius or Odyssey Access Client software only, Customer shall use such Software on a single computer containing a single physical random access memory space and containing any number of processors. Use of the Steel-Belted Radius software on multiple computers requires multiple licenses, regardless of whether such computers are physically contained on a single chassis.
  - c. Product purchase documents, paper or electronic user documentation, and/or the particular licenses purchased by Customer may specify limits to Customer's use of the Software. Such limits may restrict use to a maximum number of seats, registered endpoints, concurrent users, sessions, calls, connections, subscribers, clusters, nodes, realms, devices, links, ports or transactions, or require the purchase of separate licenses to use particular features, functionalities, services, applications, operations, or capabilities, or provide throughput, performance, configuration, bandwidth, interface, processing, temporal, or geographical limits. In addition, such limits may restrict the use of the Software to managing certain kinds of networks or require the Software to be used only in conjunction with other specific Software. Customer's use of the Software shall be subject to all such limitations and purchase of all applicable licenses.
  - d. For any trial copy of the Software, Customer's right to use the Software expires 30 days after download, installation or use of the Software. Customer may operate the Software after the 3D-day trial period only if Customer pays for a license to do so. Customer may not extend or create an additional trial period by re-installing the Software after the 3D-day trial period.
  - e. The Global Enterprise Edition of the Steel-Belted Radius software may be used by Customer only to manage access to Customer's enterprise network. Specifically, service provider customers are expressly prohibited from using the Global Enterprise Edition of the Steel-Belted Radius software to support any commercial network access services. The foregoing license is not transferable or assignable by Customer. No license is granted herein to any user who did not originally purchase the applicable license(s) for the Software from Juniper or an authorized Juniper reseller.
4. **Use Prohibitions.** Notwithstanding the foregoing, the license provided herein does not permit the Customer to, and Customer agrees not to and shall not: (a) modify, unbundle, reverse engineer, or create derivative works based on the Software; (b) make unauthorized copies of the Software (except as necessary for backup purposes); (c) rent, sell, transfer, or grant any rights in and to any copy of the Software, in any form, to any third party; (d) remove any proprietary notices, labels, or marks on or in any copy of the Software or any product in which the Software is embedded; (e) distribute any copy of the Software to any third party, including as may be embedded in Juniper equipment sold in the secondhand market; (f) use any 'locked' or key-restricted feature, function, service, application, operation, or capability without first purchasing the applicable license(s) and obtaining a valid key from Juniper, even if such feature, function, service, application, operation, or capability is enabled without a key; (g) distribute any key for the Software provided by Juniper to any third party; (h) use the Software in any manner that extends or is broader than the uses purchased by Customer from Juniper or an authorized Juniper reseller; (i) use the Embedded Software on non-Juniper equipment; (j) use the Software (or make it available for use) on Juniper equipment that the Customer did not originally purchase from Juniper or an authorized Juniper reseller; (k) disclose the results of testing or benchmarking of the Software to any third party without the prior written consent of Juniper; or (l) use the Software in any manner other than as expressly provided herein.
5. **Audit.** Customer shall maintain accurate records as necessary to verify compliance with this Agreement. Upon request by Juniper, Customer shall furnish such records to Juniper and certify its compliance with this Agreement.
6. **Confidentiality.** The Parties agree that aspects of the Software and associated documentation are the confidential property of Juniper. As such, Customer shall exercise all reasonable commercial efforts to maintain the Software and associated documentation in confidence, which at a minimum includes restricting access to the Software to Customer employees and contractors having a need to use the Software for Customer's internal business purposes.
7. **Ownership.** Juniper and Juniper's licensors, respectively, retain ownership of all right, title, and interest (including copyright) in and to the Software, associated documentation, and all copies of the Software. Nothing in this Agreement constitutes a transfer or conveyance of any right, title, or interest in the Software or associated documentation, or a sale of the Software, associated documentation, or copies of the Software.

**8. Warranty, Limitation of Liability, Disclaimer of Warranty.** The warranty applicable to the Software shall be as set forth in the warranty statement that accompanies the Software (the "Warranty Statement"). Nothing in this Agreement shall give rise to any obligation to support the Software. Support services may be purchased separately. Any such support shall be governed by a separate, written support services agreement. TO THE MAXIMUM EXTENT PERMITTED BY LAW, JUNIPER SHALL NOT BE LIABLE FOR ANY LOST PROFITS, LOSS OF DATA, OR COSTS OR PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES, OR FOR ANY SPECIAL, INDIRECT, OR CONSEQUENTIAL DAMAGES ARISING OUT OF THIS AGREEMENT, THE SOFTWARE, OR ANY JUNIPER OR JUNIPER-SUPPLIED SOFTWARE. IN NO EVENT SHALL JUNIPER BE LIABLE FOR DAMAGES ARISING FROM UNAUTHORIZED OR IMPROPER USE OF ANY JUNIPER OR JUNIPER-SUPPLIED SOFTWARE. EXCEPT AS EXPRESSLY PROVIDED IN THE WARRANTY STATEMENT TO THE EXTENT PERMITTED BY LAW, JUNIPER DISCLAIMS ANY AND ALL WARRANTIES IN AND TO THE SOFTWARE (WHETHER EXPRESS, IMPLIED, STATUTORY, OR OTHERWISE), INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NONINFRINGEMENT. IN NO EVENT DOES JUNIPER WARRANT THAT THE SOFTWARE, OR ANY EQUIPMENT OR NETWORK RUNNING THE SOFTWARE, WILL OPERATE WITHOUT ERROR OR INTERRUPTION, OR WILL BE FREE OF VULNERABILITY TO INTRUSION OR ATTACK. In no event shall Juniper's or its suppliers' or licensors' liability to Customer, whether in contract, tort (including negligence), breach of warranty, or otherwise, exceed the price paid by Customer for the Software that gave rise to the claim, or if the Software is embedded in another Juniper product, the price paid by Customer for such other product. Customer acknowledges and agrees that Juniper has set its prices and entered into this Agreement in reliance upon the disclaimers of warranty and the limitations of liability set forth herein, that the same reflect an allocation of risk between the Parties (including the risk that a contract remedy may fail of its essential purpose and cause consequential loss), and that the same form an essential basis of the bargain between the Parties.

**9. Termination.** Any breach of this Agreement or failure by Customer to pay any applicable fees due shall result in automatic termination of the license granted herein. Upon such termination, Customer shall destroy or return to Juniper all copies of the Software and related documentation in Customer's possession or control.

**10. Taxes.** All license fees for the Software are exclusive of taxes, withholdings, duties, or levies (collectively "Taxes"). Customer shall be responsible for paying Taxes arising from the purchase of the license, or importation or use of the Software.

**11. Export.** Customer agrees to comply with all applicable export laws and restrictions and regulations of any United States and any applicable foreign agency or authority, and not to export or re-export the Software or any direct product thereof in violation of any such restrictions, laws or regulations, or without all necessary approvals. Customer shall be liable for any such violations. The version of the Software supplied to Customer may contain encryption or other capabilities restricting Customer's ability to export the Software without an export license.

**12. Commercial Computer Software.** The Software is "commercial computer software" and is provided with restricted rights. Use, duplication, or disclosure by the United States government is subject to restrictions set forth in this Agreement and as provided in DFARS 227.7201 through 227.7202-4, FAR 12.212, FAR 27.405(b)(2), FAR 52.227-19; or FAR 52.227-14(ALT III) as applicable.

**13. Interface Information.** To the extent required by applicable law, and at Customer's written request, Juniper shall provide Customer with the interface information needed to achieve interoperability between the Software and another independently created program, on payment of applicable fee, if any. Customer shall observe strict obligations of confidentiality with respect to such information and shall use such information in compliance with any applicable terms and conditions upon which Juniper makes such information available.

**14. Third Party Software.** Any licensor of Juniper whose software is embedded in the Software and any supplier of Juniper whose products or technology are embedded in (or services are accessed by) the Software shall be a third party beneficiary with respect to this Agreement, and such licensor or vendor shall have the right to enforce this Agreement in its own name as if it were Juniper. In addition, certain third party software may be provided with the Software and is subject to the accompanying license(s), if any, of its respective owner(s). To the extent portions of the Software are distributed under and subject to open source licenses obligating Juniper to make the source code for such portions publicly available (such as the GNU General Public License ("GPL") or the GNU Library General Public License ("LGPL")), Juniper will make such source code portions (including Juniper modifications, as appropriate) available upon request for a period of up to three years from the date of distribution. Such request can be made in writing to Juniper Networks, Inc., 1194 N. Mathilda Ave., Sunnyvale, CA 94089, ATTN: General Counsel. You may obtain a copy of the GPL at <http://www.gnu.org/licenses/gpl.html>. and a copy of the LGPL at <http://www.gnu.org/licenses/lgpl.html>.

**15. Miscellaneous.** This Agreement shall be governed by the laws of the State of California without reference to its conflicts of laws principles. The provisions of the U.N. Convention for the International Sale of Goods shall not apply to this Agreement. For any disputes arising under this Agreement, the Parties hereby consent to the personal and exclusive jurisdiction of, and venue in, the state and federal courts within Santa Clara County, California. This Agreement constitutes the entire and sole agreement between Juniper and the Customer with respect to the Software, and supersedes all prior and contemporaneous agreements relating to the Software, whether oral or written (including any inconsistent terms contained in a purchase order), except that the terms of a separate written agreement executed by an authorized Juniper representative and Customer shall govern to the extent such terms are inconsistent or conflict with terms contained herein. No modification to this Agreement nor any waiver of any rights hereunder shall be effective unless expressly assented to in writing by the party to be charged. If any portion of this Agreement is held invalid, the Parties agree that such invalidity shall not affect the validity of the remainder of this Agreement. This Agreement and associated documentation has been written in the English language, and the Parties agree that the English version will govern. (For Canada: Les parties aux présentes confirment leur volonté que cette convention de même que tous les documents y compris tout avis qui s'y rattache, soient rédigés en langue anglaise. (Translation: The parties confirm that this Agreement and all related documentation are and will be in the English language)).

# Client-Side Application Changes Guide

This guide lists the names of the package files used by the Infranet Controller to install client-side components, the names of the files the packages install and uninstall, and the registry changes the files make to the user's system. It also describes the permissions that are required to install and run various Infranet Controller client-side components.

- “Juniper Unified Network Services” on page 1
- “Odyssey Access Client on Windows XP and Windows Vista 32-bit” on page 3
- “Odyssey Access Client on Windows Vista 64-bit” on page 33
- “Odyssey Access Client on Macintosh” on page 39
- “Host Checker” on page 102

## ***Juniper Unified Network Services***

The UAC Agent installer includes the Juniper Unified Network Service. The Juniper Unified Network Services provides a wide array of core network and security services including encryption, Layer 3 enforcement, and an infrastructure to download, install, upgrade, and execute Juniper-signed client-side applications without Administrator privileges.

### **Package file and file location**

C:\Windows\Downloaded Program Files\JuniperSetup.ocx

### **Additional files installed by package and file locations**

The Juniper Unified Network Service installs the following additional files in the C:\Program Files\Common Files\Juniper Networks\JUNS directory:

- access.ini
- versionInfo.ini
- dbghelp.dll
- dsAccessService.exe
- dsInstallerService.dll
- dsLogService.dll

- Uninstall.exe
- install.log
- JuniperSetupClientOCX.exe
- JuniperSetupOCX.exe
- uninstall.exe.manifest

### **Files remaining after uninstall**

- install.log
- JuniperSetupClientOCX

### **Registry modifications**

The Juniper Unified Network Service sets the following value in HKLM\Software\Juniper Networks\Common Files\dsLogService

- String dsLogService. Set to %Program Files%\Common Files\Juniper Networks\JUNS\dsLogService.dll.

The Juniper Unified Network Service sets the following values in HKLM\Software\Juniper Networks\Logging\Level

- String Level. Set to “3”
- String LogFileName. Set to “%DocumentsAndSettings%\All Users\Application Data\Juniper Networks\Logging\debuglog.log”
- String LogSize. Set to “10”

The Juniper Unified Network Service sets the following values in HKLM\System\CurrentControlSet\Service\JuniperAccessService\Description

- String Description. Set to “Manages Juniper Networks Software”
- String Displayname. Set to “Juniper Unified Network Service”
- Dword Error Control. Set to “0x00000000”
- String Failure Actions. Set to “Binary Data”
- String ImagePath. Set to “%Program Files%\Common Files\Juniper Networks\JUNS\dsAccessService.exe”
- String ObjectName. Set to “LocalSystem”
- Dword Start. Set to “0x00000002”
- Dword Type. Set to “0x00000110”

The Juniper Unified Network Service sets the following values in HKLM\System\CurrentControlSet\Service\JuniperAccessService\Description

- String 0. Set to “Root\LEGACY\_JUNIPERACCESSSERVICE\0000”
- Dword Count. Set to “0x00000001”
- Dword NextInstance. Set to “0x00000001”
- String Security. Set to “Binary Data”

## **Tunnel Manager**

### ***Files installed and file locations***

Tunnel Manager installs the following additional files in the C:\Program Files\Common Files\Juniper Networks\Tunnel Manager directory:

- dstmclient.dll
- dstmservice.dll
- dstunnelmanager.dll
- tm.dep
- uninstall.exe
- versioninfo.ini
- install.log
- uninstall.exe.manifest

### ***Files remaining after uninstall***

- install.log

### ***Registry modifications***

Tunnel manager sets the following values in HKEY\_LOCAL\_MACHINE\SOFTWARE\Juniper Networks\Common Files:

- String dsTMClient. Set to C:\Program Files\Common Files\Juniper Networks\Tunnel Manager\dsTMClient.dll
- String dsTunnelManager. Set to C:\Program Files\Common Files\Juniper Networks\Tunnel Manager\dsTunnelManager.dll

## **Odyssey Access Client on Windows XP and Windows Vista 32-bit**

To run the Odyssey Access Client, the Infranet Controller downloads the OdysseyAccessClient.msi package to the user’s client. This package is responsible for downloading additional files to the user’s system in order to run the Odyssey Access Client.

### **Package file and file location**

The OdysseyAccessClient.msi package is installed in C:\Documents and Settings\All Users\Application Data\Juniper Networks\UAC Agent\.

The Odyssey Access Client application is installed in C:\Program Files\Juniper Networks\Odyssey Access Client\odClientService.exe.

### **Files remaining after uninstall**

- C:\WINDOWS\system32\drivers\jnprvamgr.sys
- C:\WINDOWS\system32\drivers\jnprva.sys

### **Additional files installed by package and file locations**

The Odyssey Access Client installs the following files on the client in the C:\Program Files\Common Files\Funk Software directory:

- dcfDOM.dll
- dcfLibrary.dll
- odCert\_M.dll
- odConsole.dll
- odFips.dll
- odFips.dll.icv
- odLib\_OSSL.dll
- odShadow.dll

On Windows XP The Odyssey Access Client installs the following files on the client in the C:\Program Files\Common Files\Juniper Networks\JNPRNA directory:

- jnprna.cat
- jnprna.dll
- jnprna.inf
- jnprna.sys
- jnprna\_m.cat
- jnprna\_M.inf
- jnprnaapi.dll
- jnprnaNetInstall.dll
- jnprva.inf
- jnprvamgr.dll
- nsStatsDump.exe

- uninst.exe
- versionInfo.ini
- install.log

In Windows Vista (32-bit), the Odyssey Access Client installs the following files on the client in the C:\Program Files\Common Files\Juniper Networks\JNPRNA directory:

- DriverUI.exe
- jnprna.cat
- jnprna.inf
- jnprna.sys
- jnprna\_m.cat
- jnprna\_m.inf
- jnprnaapi.dll
- jnprnaNetInstall.dll
- jnprnaNetInstallTest.exe
- jnprva.cat
- jnprva.inf
- jnprva.sys
- jnprvamgr.cat
- jnprvamgr.dll
- jnprvamgr.inf
- jvaTest.exe
- nsStatsDump.exe
- uninst.exe
- x64/jnprNetInstall.dll
- install.log
- versionInfo.ini

#### **Files remaining after uninstall**

- install.log

- jnprnaNetInstall.log

The Odyssey Access Client installs the following files on the client in the C:\Program Files\Common Files\Juniper Networks\JSCDT directory:

- jnprShare.dll

Additionally, in Windows Vista the following file is installed.

- jnprShare.txt
- jnprShare.lock
- jnprShare.log

The Odyssey Access Client installs the following files on the client in the C:\Program Files\Common Files\Juniper Networks\JUNS directory:

- access.ini
- DbgHelp.dll
- dsAccessService.exe
- dsInstallerService.dll
- dsLogService.dll
- JuniperSetupClientOCX.exe
- JuniperSetupOCX.exe
- Uninstall.exe
- Uninstall.exe.manifest
- versionInfo.ini

On Windows XP the Odyssey Access Client installs the following files on the client in the C:\Program Files\Common Files\Juniper Networks\TNC Client directory:

- AVManager.dll
- CAntiVirusCOM.dll
- CertAuthIMC.dll
- CFireWallCOM.dll
- dsHostCheckerResource\_DE.dll
- dsHostCheckerResource\_EN.dll
- dsHostCheckerResource\_ES.dll
- dsHostCheckerResource\_FR.dll

- dsHostCheckerResource\_JA.dll
- dsHostCheckerResource\_KO.dll
- dsHostCheckerResource\_ZH.dll
- dsHostCheckerResource\_ZH\_CN.dll
- dsnsisdll.dll
- efc.dll
- dsWinClient.dll
- EPCheck.dll
- hcimc.dll
- install.log
- jsystemimc.dll
- jTnccNarProxy.dll
- jTnccService.exe
- msvcp60.dll
- patchlinkimc.dll
- ShavlikIMC.dll
- uninstall.exe
- UnifiedSDK.ini
- versionInfo.ini

In Windows Vista (32-bit), the Odyssey Access Client installs the following files on the client in the C:\Program Files\Common Files\Juniper Networks\TNC Client directory:

- AVManager.dll
- CAntiVirusCOM.dll
- CertAuthIMC.dll
- CFireWallCOM.dll
- dsHostCheckerResource\_DE.dll
- dsHostCheckerResource\_EN.dll
- dsHostCheckerResource\_ES.dll
- dsHostCheckerResource\_FR.dll

- dsHostCheckerResource\_JA.dll
- dsHostCheckerResource\_KO.dll
- dsHostCheckerResource\_ZH.dll
- dsHostCheckerResource\_ZH\_CN.dll
- dsnsisdll.dll
- efc.dll
- dsWinClient.dll
- EPCheck.dll
- FWManager.dll
- hcimc.dll
- install.log
- jsystemimc.dll
- jTnccNarProxy.dll
- jTnccService.exe
- msvcp60.dll
- OPSWATAVCommon.dll
- OPSWATProcessesScanner.dll
- patchlinkimc.dll
- pinfo.dat
- ShavlikIMC.dll
- TNCC.dep
- uninstall.exe
- UnifiedSDK.ini
- versionInfo.inni
- hfnetchk6b.xml
- HFVersions cab file
- Manifest XML
- stPatchAssesment.dll

- stUpdateManager.dll

In Windows Vista (32-bit), the Odyssey Access Client installs the following files on the client in the C:\Program Files\Common Files\Juniper Networks\TNC Client\AV directory:

- AEC\_AV.dll
- AhnLabAS.dll
- AhnLabAV.dll
- ALWIL.dll
- AnonymizerAS.dll
- AOL.dll
- AolAV.dll
- Authentium.dll
- AuthentiumAS.dll
- BitDefenderAS.dll
- BitDefenderAV.dll
- Bullet\_Proof\_Soft.dll
- Check\_PointAS.dll
- Check\_PointAV.dll
- ClamAV.dll
- ClamWin.dll
- Computer\_Associates\_International.dll
- DefenderProAV.dll
- EarthLinkAS.dll
- EarthLinkAV.dll
- Eset.dll
- FaceTimeAS.dll
- Frisk\_Software\_International.dll
- F-SecureAV.dll
- GData.dll

- Gridsoft.dll
- HauriAV.dll
- HBEDV.dll
- ISSAV.dll
- Javacool\_Software.dll
- Jiangmin.dll
- Kaspersky\_Labs.dll
- KingSoft.dll
- Lavasoft.dll
- McAfeeAS.dll
- McAfeeAV.dll
- MicroSmarts.dll
- Microsoft\_Corporation.dll
- MicrosoftAV.dll
- MicroWorld.dll
- NormanAV.dll
- NortonAS.dll
- NortonAV.dll
- Panda\_Software.dll
- PC\_Tools.dll
- PestPatrol.dll
- Prevx\_Ltd.dll
- RadialPointAS.dll
- RadialPointAV.dll
- RisingAV.dll
- SalD.dll
- SBC\_Yahoo\_AntiVirus\_Component.dll
- SerenitiAS.dll

- SerenitiAV.dll
- SophosAV.dll
- SpyBot.dll
- SunbeltAS.dll
- TrendMicroAS.dll
- TrendMicroAV.dll
- VCOMAS.dll
- VCOMAV.dll
- Webroot.dll
- Yahoo.dll
- Zone\_Labs.dll

The Odyssey Access Client installs the following files on the client in the C:\Program Files\Common Files\Juniper Networks\Tunnel Manager directory:

- dsTMClient.dll
- dsTMService.dll
- dsTunnelManager.dll
- TM.dep
- Uninstall.exe
- Uninstall.exe.manifest
- versionInfo.ini

On Windows XP the Odyssey Access Client installs the following files on the client in the C:\Program Files\Juniper Networks\Odyssey Access Client directory:

- AccessServiceSetup.exe
- AccessServiceComponent.exe
- ClientPreset.xml
- dsNetworkMonitor.dll
- epdiag.dll
- jnprnaInstall.exe
- odClient.chm
- odClientAdministrator.exe

- odClientControl.dll
- odClientFE.chm
- odClientMgr.exe
- odClientMgrDialogs.dll
- odClientResource0009.dll
- odClientService.exe
- Odcpl.cpl
- odGinaLibrary.dll
- odjpaservice.dll
- odLogin.dll
- odLoginScript.exe
- odPush.dat
- odSCard.dll
- odService.dll
- odServiceDialogs.dll
- odServiceResource0009.dll
- odSuppExt.dll
- OdTray.exe
- odyEvent.dll
- odyGina.dll
- odyNwLgXctl.ocx
- readme.txt
- TnccSetup.exe
- Wrapper.exe

On Windows Vista (32-bit) the Odyssey Access Client installs the following files on the client in the C:\Program Files\Juniper Networks\Odyssey Access Client directory:

- AccessServiceSetup.exe
- AccessServiceComponent.exe
- ClientPreset.xml
- dsNetworkMonitor.dll
- epdiag.dll

- jnprnalnstall.exe
- JNPRCredProv.dll
- JNPRlhvExt.dll
- JNPRSmartCardProv.dll
- odClient.chm
- odClientAdministrator.exe
- odClientControl.dll
- odClientFE.chm
- odClientMgr.exe
- odClientMgrDialogs.dll
- odClientResource0009.dll
- odClientService.exe
- Odcpl.cpl
- odGinaLibrary.dll
- odjpaservice.dll
- odLogin.dll
- odLoginScript.exe
- odPush.dat
- odSCard.dll
- odService.dll
- odServiceDialogs.dll
- odServiceResource0009.dll
- odSuppExt.dll
- OdTray.exe
- odyNwLgXctl.ocx
- readme.txt
- TnccSetup.exe
- TunnelManagerSetup.exe
- Wrapper.exe

In Windows Vista (32-bit), the Odyssey Access Client installs the following files on the client in the C:\Program Files\Common Files\Juniper Networks\Odyssey Access Client directory:

- AccessServiceComponent.exe
- ClientPreset.xml
- dsNetworkMonitor.dll
- epdiag.dll
- JNPRCredProv.dll
- JNPRIhvExt.dll
- jnprnaInstall.exe
- JNPRSmartCardProv.dll
- odClient.chm
- odClientAdministrator.exe
- odClientControl.dll
- odClientMgr.exe
- odClientMgrDialogs.dll
- odClientResource0009.dll
- odClientService.exe
- Odcpl.cpl
- odGinaLibrary.dll
- odGinaLibrary64.dll
- odjpaservice.dll
- odLogin.dll
- odLoginScript.exe
- odPush.dat
- odSCard.dll
- odService.dll
- odServiceDialogs.dll
- odServiceResource0009.dll

- OdTray.exe
- odyEvent.dll
- odyGina.dll
- odyNwLgXctl.ocx
- readme.txt
- TnccSetup.exe
- TunnelManagerComponent.exe

### **Files remaining after uninstall**

- odInitialSettings.xml

In Windows Vista (32-bit), the Odyssey Access Client installs the following files on the client in the C:\Users\\AppData\Roaming\Juniper Networks\UAC Agent directory, and in the C:\Documents and Settings\\Application Data\Juniper Networks\UAC Agent directory:

- dsInstallerClient.dll
- dsLogService.dll
- install.log
- OACInstall.log
- remove1x.exe

In Windows XP the Odyssey Access Client installs the following file on the client in the C:\Documents and Settings\All Users\Application Data directory:

- NeoterisSetup.OCX

### **Files remaining after uninstall**

- NeoterisSetup.OCX

On Windows XP the Odyssey Access Client installs the following directory on the client:

- C:\Users\\AppData\Roaming\Juniper Networks\Infranet Agent

On Windows Vista (32-bit) the Odyssey Access Client installs the following directory on the client:

- C:\Documents and Settings\\Application Data\Juniper Networks\Infranet Agent

On Windows XP the Odyssey Access Client installs the following files on the client in the C:\Documents and Settings\\Application Data\Juniper Networks\Setup Client directory:

- JuniperSetupCtrl.log
- JuniperSetupApp.log
- JuniperSetupApp.exe
- JuniperSetupDLL.log
- odInitialScript.xml
- string\_de.properties
- string\_en.properties
- string\_es.properties
- string\_fr.properties
- string\_ja.properties
- string\_ko.properties
- string\_zh.properties
- string\_zh\_cn.properties
- versionInfo.ini
- NeoterisSetup.ocx
- JuniperSetupCtrl.log
- JuniperSetupClient.ini
- JuniperSetupDLL.log
- JuniperSetupClientOCX.exe
- JuniperSetupDLL.dll
- dsLogService.dll

In Windows Vista (32-bit), the Odyssey Access Client installs the following files on the client in the C:\Users\\AppData\Roaming\Juniper Networks\Setup Client directory:

- dsLogService.dll
- JuniperSetupClient.exe
- JuniperSetupClient.log
- JuniperSetupClient.ini
- JuniperSetupClientOCX.exe

- JuniperSetupDLL.dll
- uninstallOCX.exe
- Client\newScripts

The Odyssey Access Client installs the following directory on the client:

- C:\Documents and Settings\\Application Data\Funk software\Odyssey
- C:\Users\\AppData\Roaming\Funk Software\Odyssey\newScripts
- C:\Documents and Settings\All Users\Application Data\Juniper Networks\Logging

The Odyssey Access Client installs the following files on the client in the C:\WINDOWS\System32\drivers directory:

- jnprna.sys
- jnprvamgr.sys
- odFIPS.sys
- odFIPS.sys.icv
- The Virtual Adapter driver, jnprva.sys (installed On-Demand)

#### **Files remaining after uninstall**

- Jnprvamgr.sys
- Jnprva.sys (will remain only if installed)

The Odyssey Access Client installs the following files on the client in the C:\Documents and Settings\\Application Data\Juniper Networks directory:

- SetupVersionInfo.ini

On Windows XP the Odyssey Access Client installs the following files on the client in the C:\Documents and Settings\All Users\Application Data\Juniper Networks\UAC Agent directory:

- oac.tmp

In Windows Vista (32-bit), the Odyssey Access Client installs the following hidden file on the client in the C:\ProgramData\Juniper Networks\UAC Agent directory:

- OACUninstall.log

#### **Files remaining after uninstall**

- OACUninstall.log

The Odyssey Access Client installs the following files on the client in the C:\Program Files\Juniper Networks\UAC Agent directory:

- UACAgent.dep
- versionInfo.ini

The Odyssey Access Client installs the following files on the client in the C:\Windows\System32\drivers directory:

- jnprna.sys
- odFIPS.sys
- odFIPS.sys.icv

The Odyssey Access Client installs the following files on the client in the C:\Windows\System32\drivers directory:

- odFIPS.sys
- odFIPS.sys.icv

The Odyssey Access Client installs the following files on the client in the C:\Windows\System32 directory:

- msvc80.dll
- msvc60.dll
- msvc80.dll
- msucr80.dll
- msucr.dll
- Odcpl.cpl
- odSendPacket.dll

The Odyssey Access Client installs the following file on the client in the C:\Windows\Documents and Settings\\Application Data\Juniper Networks\Setup directory:

- odInitialScript.xml

In Windows Vista (32-bit), the Odyssey Access Client installs the following files on the client in the C:\Windows\winxs\Manifests directory:

- x86\_Microsoft.VC80.CRT\_1fc8b3b9a1e18e3b\_8.0.50727.762\_x-ww\_6b128700.cat
- x86\_Microsoft.VC80.CRT\_1fc8b3b9a1e18e3b\_8.0.50727.762\_x-ww\_6b128700.manifest

In Windows Vista (32-bit), the Odyssey Access Client installs the following files on the client in the

C:\Windows\winxs\Policies\x86\_policy.80.Microsoft.VC80.CRT\_1fc8b3b9a1e18e3b\_x-ww\_77c24773 directory:

- 8.0.50727.762.cat
- 7.0.50727.762.policy

In Windows Vista (32-bit), the Odyssey Access Client installs the following files on the client in the

C:\Windows\winxs\x86\_microsoft.vc80.crt\_1fc8b3b9a1e18e3b\_8.0.50727.762\_none\_10b2f55f9bffb8f8 directory:

- msvcm80.dll
- msvcp80.dll
- msvcr80.dll
- x86\_Microsoft.VC80.CRT\_1fc8b3b9a1e18e3b\_8.0.50727.762\_x-ww\_6b128700.cat
- x86\_Microsoft.VC80.CRT\_1fc8b3b9a1e18e3b\_8.0.50727.762\_x-ww\_6b128700.manifest

In Windows Vista (32-bit), the Odyssey Access Client installs the following files on the client in the

C:\Windows\winxs\x86\_Microsoft\VC80.CRT\_1fc8b3b9a1e18e3b\_8.0.50727.762\_x-ww\_6b128700 directory:

- msvcm80.dll
- msvcp80.dll
- msvcr80.dll

In Windows Vista (32-bit), the Odyssey Access Client installs the following files on the client in the

C:\Windows\winxs\x86\_policy.8.0.microsoft.vc80.crt\_1fc8b3b9a1e18e3b\_8.0.50727.762\_none\_9193a620671dde41 directory:

- 8.0.50727.762.cat
- 8.0.50727.762.policy

### Registry modifications

The Odyssey Access Client sets the following registry files:

- String Default is set to “ConfigUI Class” in HKEY\_CLASSES\_ROOT\odClientMgrDialogs.ConfigUI
- String Default is set to “{473D6B6A-AA07-4098-8546-1A15D020F9EE}” in HKEY\_CLASSES\_ROOT\odClientMgrDialogs.ConfigUI\CLSID

- String Default is set to “odClientMgrDialogs.ConfigUI.1” in HKEY\_CLASSES\_ROOT\odClientMgrDialogs.ConfigUI\CurVer
- String Default is set to “ConfigUI Class” in HKEY\_CLASSES\_ROOT\odClientMgrDialogs.ConfigUI.1
- String Default is set to “{473D6B6A-AA07-4098-8546-1A15D020F9EE}” in HKEY\_CLASSES\_ROOT\odClientMgrDialogs.ConfigUI.1\CLSID
- String Default is set to “OdConsoleDialog Class” in HKEY\_CLASSES\_ROOT\CLSID\{6B891951-71B6-405E-B9E8-3250FCF4BC51}
- String Default is set to “CommonFilesFolder]Funk Software\odConsole.dll” and string ThreadingModel is set to “Free” in HKEY\_CLASSES\_ROOT\CLSID\{6B891951-71B6-405E-B9E8-3250FCF4BC51}\InprocServer32
- String Default is set to “OdConsole.OdConsoleDialog.1” in HKEY\_CLASSES\_ROOT\CLSID\{6B891951-71B6-405E-B9E8-3250FCF4BC51}\ProgID
- String Default is set to “{17689671-9839-463D-9DAC-2800AA4D74F5}” in HKEY\_CLASSES\_ROOT\CLSID\{6B891951-71B6-405E-B9E8-3250FCF4BC51}\TypeLib
- String Default is set to “OdClientControl.OdClientConfigurationDatabase” in HKEY\_CLASSES\_ROOT\CLSID\{6B891951-71B6-405E-B9E8-3250FCF4BC51}\VersionIndependentProgID
- String Default is set to “OdConsoleLogStream Class” in HKEY\_CLASSES\_ROOT\CLSID\{CBBFB98A-CC29-440E-A62F-ADD5C69D25DC}
- String Default is set to “[CommonFilesFolder]Funk Software\odConsole.dll” and String ThreadingModel is set to “Free” in HKEY\_CLASSES\_ROOT\CLSID\{CBBFB98A-CC29-440E-A62F-ADD5C69D25DC}\InprocServer32
- String Default is set to “OdConsole.OdConsoleLogStream.1” in HKEY\_CLASSES\_ROOT\CLSID\{CBBFB98A-CC29-440E-A62F-ADD5C69D25DC}\ProgID
- String Default is set to “{6D396288-D452-4869-9895-4EEE4D3C8CF4}” in HKEY\_CLASSES\_ROOT\CLSID\{CBBFB98A-CC29-440E-A62F-ADD5C69D25DC}\TypeLib
- String Default is set to “OdConsole.OdConsoleLogStream” in HKEY\_CLASSES\_ROOT\CLSID\{CBBFB98A-CC29-440E-A62F-ADD5C69D25DC}\VersionIndependentProgID
- String ThreadingModel is set to “Free” in HKEY\_CLASSES\_ROOT\CLSID\{03104BE6-BDDE-4FC3-B52B-869836FB408F}\InprocServer32

- String Default is set to "{3880EABE-2031-47EA-8BB7-8E9709A41D7A}" in HKEY\_CLASSES\_ROOT\CLSID\{03104BE6-BDDE-4FC3-B52B-869836FB408F}\TypeLib
- String Default is set to "OdClientEngine Class" in HKEY\_CLASSES\_ROOT\CLSID\{0A3937EA-5A82-4363-A0CD-4245773C282C}
- String Default is set to "[INSTALLDIR]odClientControl.dll" and String ThreadingModel is set to "Both" in HKEY\_CLASSES\_ROOT\CLSID\{0A3937EA-5A82-4363-A0CD-4245773C282C}\InprocServer32
- String Default is set to "OdClientControl.OdClientEngine.1" in HKEY\_CLASSES\_ROOT\CLSID\{0A3937EA-5A82-4363-A0CD-4245773C282C}\ProgID
- Creates the key HKEY\_CLASSES\_ROOT\CLSID\{0A3937EA-5A82-4363-A0CD-4245773C282C}\Programmable
- String Default is set to "{17689671-9839-463D-9DAC-2800AA4D74F5}" in HKEY\_CLASSES\_ROOT\CLSID\{0A3937EA-5A82-4363-A0CD-4245773C282C}\TypeLib
- String Default is set to "OdClientControl.OdClientEngine" in HKEY\_CLASSES\_ROOT\CLSID\{0A3937EA-5A82-4363-A0CD-4245773C282C}\VersionIndependentProgID
- String Default is set to "OdClientConfigurationDatabase Class" in HKEY\_CLASSES\_ROOT\CLSID\{CF890798-FED6-49D3-A1F5-947BD485CC03}
- String Default is set to "[INSTALLDIR]odClientControl.dll" and String ThreadingModel is set to "Both" in HKEY\_CLASSES\_ROOT\CLSID\{CF890798-FED6-49D3-A1F5-947BD485CC03}\InprocServer32
- String Default is set to "OdClientControl.OdClientConfigurationDatabase.1" in HKEY\_CLASSES\_ROOT\CLSID\{CF890798-FED6-49D3-A1F5-947BD485CC03}\ProgID
- Creates the key HKEY\_CLASSES\_ROOT\CLSID\{CF890798-FED6-49D3-A1F5-947BD485CC03}\Programmable
- String Default is set to "{17689671-9839-463D-9DAC-2800AA4D74F5}" in HKEY\_CLASSES\_ROOT\CLSID\{CF890798-FED6-49D3-A1F5-947BD485CC03}\TypeLib
- String Default is set to "OdClientControl.OdClientConfigurationDatabase" in HKEY\_CLASSES\_ROOT\CLSID\{CF890798-FED6-49D3-A1F5-947BD485CC03}\VersionIndependentProgID
- String Default is set to "OdClientSecurityDatabase Class" in HKEY\_CLASSES\_ROOT\CLSID\{F24A7852-937D-4D9D-9086-8B976FE979E8}
- String Default is set to "[INSTALLDIR]odClientControl.dll" and String ThreadingModel is set to "Both" in HKEY\_CLASSES\_ROOT\CLSID\{F24A7852-937D-4D9D-9086-8B976FE979E8}\InprocServer32

- String Default is set to “OdClientControl.OdClientSecurityDatabase.1” in HKEY\_CLASSES\_ROOT\CLSID\{F24A7852-937D-4D9D-9086-8B976FE979E8}\ProgID
- Creates the key HKEY\_CLASSES\_ROOT\CLSID\{F24A7852-937D-4D9D-9086-8B976FE979E8}\Programmable
- String Default is set to “{17689671-9839-463D-9DAC-2800AA4D74F5}” in HKEY\_CLASSES\_ROOT\CLSID\{F24A7852-937D-4D9D-9086-8B976FE979E8}\TypeLib
- String Default is set to “OdClientControl.OdClientSecurityDatabase” in HKEY\_CLASSES\_ROOT\CLSID\{F24A7852-937D-4D9D-9086-8B976FE979E8}\VersionIndependentProgID
- String Default is set to “OdysseyEngine Class” in HKEY\_CLASSES\_ROOT\CLSID\{C4BB5277-BC02-4DE6-846F-E18A50095DF6}
- String Default is set to “[INSTALLDIR]odService.dll” and String ThreadingModel is set to “Free” in HKEY\_CLASSES\_ROOT\CLSID\{C4BB5277-BC02-4DE6-846F-E18A50095DF6}\InprocServer32
- String Default is set to “OdService.OdysseyEngine.1” in HKEY\_CLASSES\_ROOT\CLSID\{C4BB5277-BC02-4DE6-846F-E18A50095DF6}\ProgID
- String Default is set to “{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}” in HKEY\_CLASSES\_ROOT\CLSID\{C4BB5277-BC02-4DE6-846F-E18A50095DF6}\TypeLib
- String Default is set to “OdService.OdysseyEngine” in HKEY\_CLASSES\_ROOT\CLSID\{C4BB5277-BC02-4DE6-846F-E18A50095DF6}\VersionIndependentProgID
- String Default is set to “ConfigUI Class” in HKEY\_CLASSES\_ROOT\CLSID\{473D6B6A-AA07-4098-8546-1A15D020F9EE}
- String Default is set to “[INSTALLDIR]odClientMgrDialogs.dll” and String ThreadingModel is set to “Both” in HKEY\_CLASSES\_ROOT\CLSID\{473D6B6A-AA07-4098-8546-1A15D020F9EE}\InprocServer32
- String Default is set to “odClientMgrDialogs.ConfigUI.1” in HKEY\_CLASSES\_ROOT\CLSID\{473D6B6A-AA07-4098-8546-1A15D020F9EE}\ProgID
- String Default is set to “{EDA6503C-E7A9-4BD0-9A2A-79466C41FF88}” in HKEY\_CLASSES\_ROOT\CLSID\{473D6B6A-AA07-4098-8546-1A15D020F9EE}\TypeLib
- String Default is set to “odClientMgrDialogs.ConfigUI” in HKEY\_CLASSES\_ROOT\CLSID\{473D6B6A-AA07-4098-8546-1A15D020F9EE}\VersionIndependentProgID
- String Default is set to “OdServiceDialogMgr Class” in HKEY\_CLASSES\_ROOT\CLSID\{71486BF6-30BD-4D9B-AD24-3AF8854B7D1E}

- String Default is set to “[INSTALLDIR]odServiceDialogs.dll” and String ThreadingModel is set to “Both” in HKEY\_CLASSES\_ROOT\CLSID\{71486BF6-30BD-4D9B-AD24-3AF8854B7D1E}\InprocServer32
- String Default is set to “OdServiceDialogs.OdServiceDialogMgr.1” in HKEY\_CLASSES\_ROOT\CLSID\{71486BF6-30BD-4D9B-AD24-3AF8854B7D1E}\ProgID
- Creates the key HKEY\_CLASSES\_ROOT\CLSID\{71486BF6-30BD-4D9B-AD24-3AF8854B7D1E}\Programmable
- String Default is set to “{2CC76071-B27F-49F1-9C3C-237DD3461A70}” in HKEY\_CLASSES\_ROOT\CLSID\{71486BF6-30BD-4D9B-AD24-3AF8854B7D1E}\TypeLib
- String Default is set to “OdServiceDialogs.OdServiceDialogMgr” in HKEY\_CLASSES\_ROOT\CLSID\{71486BF6-30BD-4D9B-AD24-3AF8854B7D1E}\VersionIndependentProgID
- String Default is set to “OdConsoleDialog Class” in HKEY\_CLASSES\_ROOT\OdConsole.OdConsoleDialog
- String Default is set to “{6B891951-71B6-405E-B9E8-3250FCF4BC51}” in HKEY\_CLASSES\_ROOT\OdConsole.OdConsoleDialog\CLSID
- String Default is set to “OdConsole.OdConsoleDialog.1” in HKEY\_CLASSES\_ROOT\OdConsole.OdConsoleDialog\CurVer
- String Default is set to “OdConsoleDialog Class” in HKEY\_CLASSES\_ROOT\OdConsole.OdConsoleDialog.1
- String Default is set to “{6B891951-71B6-405E-B9E8-3250FCF4BC51}” in HKEY\_CLASSES\_ROOT\OdConsole.OdConsoleDialog.1\CLSID
- String Default is set to “OdConsoleLogStream Class” in HKEY\_CLASSES\_ROOT\OdConsole.OdConsoleLogStream
- String Default is set to “{CBBFB98A-CC29-440E-A62F-ADD5C69D25DC}” in HKEY\_CLASSES\_ROOT\OdConsole.OdConsoleLogStream\CLSID
- String Default is set to “OdConsole.OdConsoleLogStream.1” in HKEY\_CLASSES\_ROOT\OdConsole.OdConsoleLogStream\CurVer
- String Default is set to “OdConsoleLogStream Class” in HKEY\_CLASSES\_ROOT\OdConsole.OdConsoleLogStream.1
- String Default is set to “{CBBFB98A-CC29-440E-A62F-ADD5C69D25DC}” in HKEY\_CLASSES\_ROOT\OdConsole.OdConsoleLogStream.1\CLSID
- Creates the key HKEY\_CLASSES\_ROOT\TypeLib
- Creates the key HKEY\_CLASSES\_ROOT\TypeLib\{6D396288-D452-4869-9895-4EEE4D3C8CF4}

- String Default is set to “odConsole 1.0 Type Library” in HKEY\_CLASSES\_ROOT\TypeLib\{6D396288-D452-4869-9895-4EEE4D3C8CF4}\1.0
- Creates the key HKEY\_CLASSES\_ROOT\TypeLib\{6D396288-D452-4869-9895-4EEE4D3C8CF4}\1.0\0
- String Default is set to “[CommonFilesFolder]Funk Software\odConsole.dll” in HKEY\_CLASSES\_ROOT\TypeLib\{6D396288-D452-4869-9895-4EEE4D3C8CF4}\1.0\0\win32
- String Default is set to “0” in HKEY\_CLASSES\_ROOT\TypeLib\{6D396288-D452-4869-9895-4EEE4D3C8CF4}\1.0\FLAGS
- String Default is set to “[CommonFilesFolder]Funk Software\” in HKEY\_CLASSES\_ROOT\TypeLib\{6D396288-D452-4869-9895-4EEE4D3C8CF4}\1.0\HELPPDIR
- Creates the key HKEY\_CLASSES\_ROOT\Interface
- String Default is set to “IConfigUI” in HKEY\_CLASSES\_ROOT\Interface\{56618E3B-08D0-41ED-B0E4-0DC9CBC5624A}
- String Default is set to “{EDA6503C-E7A9-4BD0-9A2A-79466C41FF88}” and String Version is set to “1.0” in HKEY\_CLASSES\_ROOT\Interface\{56618E3B-08D0-41ED-B0E4-0DC9CBC5624A}\TypeLib
- String Default is set to “{00020424-0000-0000-C000-000000000046}” in HKEY\_CLASSES\_ROOT\Interface\{56618E3B-08D0-41ED-B0E4-0DC9CBC5624A}\ProxyStubClsid
- String Default is set to “{00020424-0000-0000-C000-000000000046}” in HKEY\_CLASSES\_ROOT\Interface\{56618E3B-08D0-41ED-B0E4-0DC9CBC5624A}\ProxyStubClsid32
- String Default is set to “IOdGinaDialog” in HKEY\_CLASSES\_ROOT\Interface\{B5717F1F-4373-432D-9089-6370558A24B6}
- String Default is set to “{00020424-0000-0000-C000-000000000046}” in HKEY\_CLASSES\_ROOT\Interface\{B5717F1F-4373-432D-9089-6370558A24B6}\ProxyStubClsid
- String Default is set to “{00020424-0000-0000-C000-000000000046}” in HKEY\_CLASSES\_ROOT\Interface\{B5717F1F-4373-432D-9089-6370558A24B6}\ProxyStubClsid32
- String Default is set to “{EDA6503C-E7A9-4BD0-9A2A-79466C41FF88}” in HKEY\_CLASSES\_ROOT\Interface\{B5717F1F-4373-432D-9089-6370558A24B6}\TypeLib
- Creates the key HKEY\_CLASSES\_ROOT\AppID
- String LocalService is set to “odClientService “ and String ServiceParameters is set to “-Service” in HKEY\_CLASSES\_ROOT\AppID\{9A2EB1DF-613A-4605-B94C-F6E9F1B83B53}

- String Default is set to “OdClientSecurityDatabase Class” in HKEY\_CLASSES\_ROOT\OdClientControl.OdClientSecurityDatabase
- String Default is set to “{F24A7852-937D-4D9D-9086-8B976FE979E8}” in HKEY\_CLASSES\_ROOT\OdClientControl.OdClientSecurityDatabase\CLSID
- String Default is set to “OdClientControl.OdClientSecurityDatabase.1” in HKEY\_CLASSES\_ROOT\OdClientControl.OdClientSecurityDatabase\CurVer
- String Default is set to “OdClientEngine Class” in HKEY\_CLASSES\_ROOT\OdClientControl.OdClientEngine.1
- String Default is set to “{0A3937EA-5A82-4363-A0CD-4245773C282C}” in HKEY\_CLASSES\_ROOT\OdClientControl.OdClientEngine.1\CLSID
- String Default is set to “OdClientConfigurationDatabase Class” in HKEY\_CLASSES\_ROOT\OdClientControl.OdClientConfigurationDatabase
- String Default is set to “{CF890798-FED6-49D3-A1F5-947BD485CC03}” in HKEY\_CLASSES\_ROOT\OdClientControl.OdClientConfigurationDatabase\CLSID
- String Default is set to “OdClientControl.OdClientConfigurationDatabase.1” in HKEY\_CLASSES\_ROOT\OdClientControl.OdClientConfigurationDatabase\CurVer
- String Default is set to “OdClientSecurityDatabase Class” in HKEY\_CLASSES\_ROOT\OdClientControl.OdClientSecurityDatabase.1
- String Default is set to “{F24A7852-937D-4D9D-9086-8B976FE979E8}” in HKEY\_CLASSES\_ROOT\OdClientControl.OdClientSecurityDatabase.1\CLSID
- String Default is set to “OdClientEngine Class” in HKEY\_CLASSES\_ROOT\OdClientControl.OdClientEngine
- String Default is set to “{0A3937EA-5A82-4363-A0CD-4245773C282C}” in HKEY\_CLASSES\_ROOT\OdClientControl.OdClientEngine\CLSID
- String Default is set to “OdClientControl.OdClientEngine.1” in HKEY\_CLASSES\_ROOT\OdClientControl.OdClientEngine\CurVer
- String Default is set to “OdClientConfigurationDatabase Class” in HKEY\_CLASSES\_ROOT\OdClientControl.OdClientConfigurationDatabase.1
- String Default is set to “{CF890798-FED6-49D3-A1F5-947BD485CC03}” in HKEY\_CLASSES\_ROOT\OdClientControl.OdClientConfigurationDatabase.1\CLSID
- String Default is set to “OdysseyEngine Class” in HKEY\_CLASSES\_ROOT\OdService.OdysseyEngine
- String Default is set to “{C4BB5277-BC02-4DE6-846F-E18A50095DF6}” in HKEY\_CLASSES\_ROOT\OdService.OdysseyEngine\CLSID
- String Default is set to “OdService.OdysseyEngine.1” in HKEY\_CLASSES\_ROOT\OdService.OdysseyEngine\CurVer

- String Default is set to “OdysseyEngine Class” in HKEY\_CLASSES\_ROOT\OdService.OdysseyEngine.1
- String Default is set to “{C4BB5277-BC02-4DE6-846F-E18A50095DF6}” in HKEY\_CLASSES\_ROOT\OdService.OdysseyEngine.1\CLSID
- String Default is set to “OdServiceDialogMgr Class” in HKEY\_CLASSES\_ROOT\OdServiceDialogs.OdServiceDialogMgr
- String Default is set to “{71486BF6-30BD-4D9B-AD24-3AF8854B7D1E}” in HKEY\_CLASSES\_ROOT\OdServiceDialogs.OdServiceDialogMgr\CLSID
- String Default is set to “OdServiceDialogs.OdServiceDialogMgr.1” in HKEY\_CLASSES\_ROOT\OdServiceDialogs.OdServiceDialogMgr\CurVer
- String Default is set to “OdServiceDialogMgr Class” in HKEY\_CLASSES\_ROOT\OdServiceDialogs.OdServiceDialogMgr.1
- String Default is set to “{71486BF6-30BD-4D9B-AD24-3AF8854B7D1E}” in HKEY\_CLASSES\_ROOT\OdServiceDialogs.OdServiceDialogMgr.1\CLSID
- Creates the key HKEY\_CURRENT\_USER\Software\Funk Software, Inc.
- Creates the key HKEY\_CURRENT\_USER\Software\Funk Software, Inc.\Odyssey
- String OdTray.exe is set to “\”[INSTALLDIR]OdTray.exe\” in HKEY\_LOCAL\_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\Run
- Creates the key HKEY\_LOCAL\_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\App Paths
- String Default is set to “[INSTALLDIR]odConfig.exe” and String Path is set to “[INSTALLDIR];[CommonFilesFolder]Funk Software” in HKEY\_LOCAL\_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\App Paths\odConfig.exe
- String Default is set to “[INSTALLDIR]OdTray.exe” and String Path is set to “[INSTALLDIR];[CommonFilesFolder]Funk Software” in HKEY\_LOCAL\_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\App Paths\OdTray.exe
- String Default is set to “[INSTALLDIR]odLoginScript.exe” and String Path is set to “[INSTALLDIR];[CommonFilesFolder]Funk Software” in HKEY\_LOCAL\_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\App Paths\odLoginScript.exe
- Creates the key HKEY\_LOCAL\_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\Control Panel
- Creates the key HKEY\_LOCAL\_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\Control Panel\Extended Properties

- Dword %SystemRoot%\System32\odcpl.cpl is set to “00000003” in HKEY\_LOCAL\_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\Control Panel\Extended Properties\{305CA226-D286-468e-B848-2B2E8E697B74} 2
- String commonFiles is set to “[CommonFilesFolder]Funk Software” in HKEY\_LOCAL\_MACHINE\SOFTWARE\Funk Software, Inc.
- Creates the key HKEY\_LOCAL\_MACHINE\SOFTWARE\Funk Software, Inc.\odyssey
- String programDirectory is set to “[INSTALLDIR]” in HKEY\_LOCAL\_MACHINE\SOFTWARE\Funk Software, Inc.\odyssey\client
- Creates the key HKEY\_LOCAL\_MACHINE\SOFTWARE\Funk Software, Inc.\odyssey\client\configuration
- String nwgina.dll is set to “1” in HKEY\_LOCAL\_MACHINE\SOFTWARE\Funk Software, Inc.\odyssey\client\configuration\ginaDLLs
- Creates the key HKEY\_LOCAL\_MACHINE\SOFTWARE\Funk Software, Inc.\odyssey\client\configuration\options
- String useOdyssey is set to “[USEODYSSEY]” and string nameType is set to “[NAMETYPE]” in HKEY\_LOCAL\_MACHINE\SOFTWARE\Funk Software, Inc.\odyssey\client\configuration\options\nwGina
- Creates the key HKEY\_LOCAL\_MACHINE\SOFTWARE\Juniper Networks
- Sets the following values in HKEY\_LOCAL\_MACHINE\SOFTWARE\Juniper Networks\Common Files:
  - String jnprnaapi. Set to “C:\Program Files\Common Files\Juniper Networks\JNPRNA\jnprnaapi.dll”
  - String nsStatsDump. Set to “C:\Program Files\Common Files\Juniper Networks\JNPRNA\nsStatsDump.exe”
  - String jnprvamgr. Set to “C:\Program Files\Common Files\Juniper Networks\JNPRNA\jnprvamgr.dll”
- Creates the key HKEY\_LOCAL\_MACHINE\SOFTWARE\Juniper Networks, Inc.
- Creates the key HKEY\_LOCAL\_MACHINE\SOFTWARE\Juniper Networks, Inc.\InstallData
- Sets the following strings in HKEY\_LOCAL\_MACHINE\SOFTWARE\Juniper Networks, Inc.\InstallData\Odyssey Access Client. Values are based on the installation:
  - ProductName
  - Manufacturer
  - LICENSEKEY
  - IS30DAY

- OEMBRANDING
- OEMLICENSEKEY
- EEINSTALL
- CommonFiles
- ISReleaseFlags
- INSTALLDIR
- PRECONFIGUREEXE
- PRECONFIGUREDMSI
- SETUPEXEDIR
- SUPPORTDIR
- DRIVERS\_DIR
- CertTempDirectory
- INSTALLGINA
- odFIPSDriverReturn

The Odyssey Access Client sets the log file location, size and filename in:

HKLM\Software\Juniper Networks\Logging

The installData registry keys are located in:

HKLM\Software\Juniper Networks\InstallData\Juniper Odyssey Access Client

### Client-side Log file location

You can enable or disable client-side logs through the **System > Log/Monitoring > Client Logs > Settings** tab of the Web console. When you enable logging, Odyssey Access Client adds log files to the following location:

C:\Documents and Settings\All Users\Application Data\Juniper Networks\Logging\

### Log files installed by the Odyssey Access Client

The Odyssey Access Client adds service log files to: C:\Documents and Settings\All Users\Application Data\Juniper Networks\Logging\debuglog.log and C:\Documents and Settings\All Users\Application Data\Juniper Networks\UAC Agent\OACInstall.log.

### Installing with Active-X or Java

If the Intranet Controller successfully installs Active-X or Java, the Odyssey Access Client installs the following additional files in the C:\Documents and Settings\<username>\Application Data\Juniper Networks\Setup directory:

- dsmmf.exe
- dsmmfres\_de.dll

- dsmmfres\_es.dll
- dsmmfres\_fr.dll
- dsmmfres\_ja.dll
- dsmmfres\_ko.dll
- dsmmfres\_zh.dll
- dsmmfres\_zh\_cn.dll
- JuniperSetupApp.exe
- JuniperSetupDLL.dll
- NeoterisSetup.ocx
- setupResource\_de.dll
- setupResource\_en.dll
- setupResource\_es.dll
- setupResource\_fr.dll
- setupResource\_ja.dll
- setupResource\_ko.dll
- setupResource\_zh.dll
- setupResource\_zh\_cn.dll
- string\_de.properties
- string\_en.properties
- string\_es.properties
- string\_fr.properties
- string\_ja.properties
- string\_ko.properties
- string\_zh.properties
- string\_zh\_cn.properties
- uninstall.exe
- versionInfo.ini

When running the installer, the following files are added to C:\Windows\Downloaded Program Files:

- JuniperSetup.inf
- JuniperSetup.ocx
- string\_en.properties
- string\_de.properties
- string\_es.properties
- string\_fr.properties
- string\_ja.properties
- string\_ko.properties
- string\_zh.properties
- string\_zh\_cn.properties

**Registry modifications**

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Code Store Database\Distribution\Units\{E5F5D008-DD2C-4D32-977D-1A0ADF03058B}:

- DWord SystemComponent. Set to "0x0000000"
- String Installer. Set to "MSICD"

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Code Store Database\Distribution\Units\{E5F5D008-DD2C-4D32-977D-1A0ADF03058B}\Contains\Files:

- String \$WINDIR\Downloaded Program Files\string\_zh\_cn.properties. Set to ""
- String \$WINDIR\Downloaded Program Files\string\_zh.properties. Set to ""
- String \$WINDIR\Downloaded Program Files\string\_ko.properties. Set to ""
- String \$WINDIR\Downloaded \Program Files\string\_ja.properties. Set to ""
- String \$WINDIR\Downloaded Program Files\string\_fr.properties. Set to ""
- String \$WINDIR\Downloaded Program Files\string\_es.properties. Set to ""
- String \$WINDIR\Downloaded Program Files\string\_de.properties. Set to ""
- String \$WINDIR\Downloaded Program Files\string\_en.properties. Set to ""
- String \$WINDIR\Downloaded Program Files\JuniperSetup.ocx. Set to ""

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Code Store Database\Distribution Units\{E5F5D008-DD2C-4D32-977D-1A0ADF03058B}\DownloadInformation:

- String CODEBASE. Set to "https://juniper.net/dana-cached/setup/JuniperSetupSP1.cab"
- String INF. Set to "\$WINDIR\Downloaded Program Files\JuniperSetup.INF"

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Code Store Database\Distribution Units\{E5F5D008-DD2C-4D32-977D-1A0ADF03058B}\InstalledVersion:

- String "". Set to "\${NEO\_PRODUCT\_VERSION}"
- String LastModified. Set to "Thu, 14 Sep 2006 07:32:24 GMT"

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\ModuleUsage\\${WINDIR/Downloaded Program Files/JuniperSetup.ocx}:

- String .Owner. Set to "{E5F5D008-DD2C-4D32-977D-1A0ADF03058B}"
- String {E5F5D008-DD2C-4D32-977D-1A0ADF03058B}. Set to ""

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\ModuleUsage\\${WINDIR/Downloaded Program Files/string\_en.properties}:

- String .Owner. Set to "{E5F5D008-DD2C-4D32-977D-1A0ADF03058B}"
- String {E5F5D008-DD2C-4D32-977D-1A0ADF03058B}. Set to ""

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\ModuleUsage\\${WINDIR/Downloaded Program Files/string\_de.properties}:

- String .Owner. Set to "{E5F5D008-DD2C-4D32-977D-1A0ADF03058B}"
- String {E5F5D008-DD2C-4D32-977D-1A0ADF03058B}. Set to ""

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\ModuleUsage\\${WINDIR/Downloaded Program Files/string\_es.properties}:

- String .Owner. Set to "{E5F5D008-DD2C-4D32-977D-1A0ADF03058B}"
- String {E5F5D008-DD2C-4D32-977D-1A0ADF03058B}. Set to ""

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\ModuleUsage\\${WINDIR/Downloaded Program Files/string\_fr.properties}:

- String .Owner. Set to "{E5F5D008-DD2C-4D32-977D-1A0ADF03058B}"
- String {E5F5D008-DD2C-4D32-977D-1A0ADF03058B}. Set to ""

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\ModuleUsage\%WINDIR\Downloaded Program Files/string\_ja.properties:

- String .Owner. Set to "{E5F5D008-DD2C-4D32-977D-1A0ADF03058B}"
- String {E5F5D008-DD2C-4D32-977D-1A0ADF03058B}. Set to ""

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\ModuleUsage\%WINDIR\Downloaded Program Files/string\_ko.properties:

- String .Owner. Set to "{E5F5D008-DD2C-4D32-977D-1A0ADF03058B}"
- String {E5F5D008-DD2C-4D32-977D-1A0ADF03058B}. Set to ""

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\ModuleUsage\%WINDIR\Downloaded Program Files/string\_zh.properties:

- String .Owner. Set to "{E5F5D008-DD2C-4D32-977D-1A0ADF03058B}"
- String {E5F5D008-DD2C-4D32-977D-1A0ADF03058B}. Set to ""

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\ModuleUsage\%WINDIR\Downloaded Program Files/string\_zh\_cn.properties:

- String .Owner. Set to "{E5F5D008-DD2C-4D32-977D-1A0ADF03058B}"
- String {E5F5D008-DD2C-4D32-977D-1A0ADF03058B}. Set to ""

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\SharedDLLs:

- Dword %WINDIR\Downloaded Program Files\string\_zh\_cn.properties. Set to "0x00000001"
- Dword %WINDIR\Downloaded Program Files\string\_zh.properties. Set to "0x00000001"
- Dword %WINDIR\Downloaded Program Files\string\_ko.properties. Set to "0x00000001"
- Dword %WINDIR\Downloaded Program Files\string\_ja.properties. Set to "0x00000001"
- Dword %WINDIR\Downloaded Program Files\string\_fr.properties. Set to "0x00000001"
- Dword %WINDIR\Downloaded Program Files\string\_es.properties. Set to "0x00000001"
- Dword %WINDIR\Downloaded Program Files\string\_de.properties. Set to "0x00000001"

- Dword \$WINDIR\Downloaded Program Files\string\_en.properties. Set to "0x00000001"
- Dword \$WINDIR\Downloaded Program Files\JuniperSetup.ocx. Set to "0x00000001"

### ***Odyssey Access Client on Windows Vista 64-bit***

In Windows Vista (64-bit), the Odyssey Access Client installs the following files on the client in the Program Files (x86)\Common Files\Funk Software directory:

- dcfDOM.dll
- dcfLibrary.dll
- odCert\_M.dll
- odConsole.dll
- odLib\_OSSL.dll
- odShadow.dll

### ***Odyssey Access Client on Windows Vista 64-bit***

In Windows Vista (64-bit), the Odyssey Access Client installs the following files on the client in the Program Files (x86)\Common Files\Juniper Networks\JNPRNA directory:

- install.log
- jnprna.cat
- jnprna.inf
- jnprna.sys
- jnprna\_m.cat
- jnprna\_m.inf
- jnprnaapi.dll
- jnprnaNetInstall.dll
- jnprnaNetInstallTest.log
- jnprva.cat
- jnprva.inf
- jnprva.sys
- jnprvamgr.cat

- jnprvamgr.dll
- jnprvamgr.inf
- jnprvamgr.sys
- nsStatsDump.exe
- uninst.exe
- versionInfo.ini

### ***Odyssey Access Client on Windows Vista 64-bit***

In Windows Vista (64-bit), the Odyssey Access Client installs the following files on the client in the Program Files (x86)\Common Files\Juniper Networks\JNPRNA\x64 directory:

- jnprna.cat
- jnprna.inf
- jnprna.sys
- jnprna\_m.cat
- jnprna\_m.inf
- jnprnaNetInstall.dll
- jnprva.cat
- jnprva.inf
- jnprva.sys
- jnprvamgr.cat
- jnprvamgr.inf
- jnprvamgr.sys

### ***Odyssey Access Client on Windows Vista 64-bit***

In Windows Vista (64-bit), the Odyssey Access Client installs the following files on the client in the Program Files (x86)\Common Files\Juniper Networks\JSCDT directory:

- jnprShare.dll
- jnprShare.lock
- jnprShare.log
- jnprShare.txt

### **Odyssey Access Client on Windows Vista 64-bit**

In Windows Vista (64-bit), the Odyssey Access Client installs the following files on the client in the Program Files (x86)\Common Files\Juniper Networks\JUNS directory:

- access.ini
- dsAccessService.exe
- dsInstallerService.dll
- dsLogService.dll
- install.log
- JuniperSetupClientOCX.exe
- JuniperSetupOCX.exe
- Uninstall.exe
- Uninstall.exe.manifest
- versionInfo.ini
- Odyssey Access Client on Windows Vista 64-bit

In Windows Vista (64-bit), the Odyssey Access Client installs the following files on the client in the Program Files (x86)\Common Files\Juniper Networks\TNC Client directory:

- AVManagerUnified.dll
- CAntiVirusCOM.dll
- CertAuthIMC.dll
- CFireWallCOM.dll
- dsHostCheckerResource\_EN.dll
- dsnsisdll.dll
- dsWinClient.dll
- efc.dat
- EPCheck.dll
- FWManager.dll
- hcimc.dll
- install.log

- jsystemimc.dll
- jTnccNarProxy.dll
- jTnccService.exe
- msvcp60.dll
- OPSWATProcessesScanner.dll
- patchlinkimc.dll
- ShavlikIMC.dll
- SoHIMC.dll
- TNCC.dep
- UnifiedSDK.ini
- uninstall.exe
- versionInfo.inni

### ***Odyssey Access Client on Windows Vista 64-bit***

In Windows Vista (64-bit), the Odyssey Access Client installs the following files on the client in the Program Files (x86)\Common Files\Juniper Networks\Tunnel Manager directory:

- dsTMClient.dll
- dsTMService.dll
- dsTunnelManager.dll
- install.log
- TM.dep
- Uninstall.exe
- Uninstall.exe.manifest
- versionInfo.ini

### ***Odyssey Access Client on Windows Vista 64-bit***

In Windows Vista (64-bit), the Odyssey Access Client installs the following files on the client in the Program Files (x86)\Juniper Networks\Odyssey Access Client directory:

- AccessServiceComponent.exe
- ClientPreset.xml

- dsNetworkMonitor.dll
- epdiag.dll
- install.log
- InstallerHelper.dll
- JNPRCredProv.dll
- JNPRHvExt.dll
- jnprnaInstall.exe
- JNPRSmartCardProv.dll
- msvcp60.dll
- odClient.chm
- odClientAdministrator.exe
- odClientControl.dll
- odClientMgr.exe
- odClientMgrDialogs.dll
- odClientResource0009.dll
- odClientService.exe
- Odcp1.cpl
- odGinaLibrary.dll
- odGinaLibrary64.dll
- odjpaservice.dll
- odLogin.dll
- odLoginScript.exe
- odPush.dat
- odSCard.dll
- odService.dll
- odServiceDialogs.dll
- odServiceResource0009.dll
- OdTray.exe

- odyEvent.dll
- odyGina.dll
- odyNwLgXctl.ocx
- readme.txt
- TnccSetup.exe
- TunnelManagerComponent.exe
- uninst.exe
- versionInfo.ini

### ***Odyssey Access Client on Windows Vista 64-bit***

In Windows Vista (64-bit), the Odyssey Access Client installs the following files on the client in the Program Files (x86)\Juniper Networks\UAC Agent directory:

- UACAgent.dep
- versionInfo.ini

### ***Odyssey Access Client on Windows Vista 64-bit***

In Windows Vista (64-bit), the Odyssey Access Client installs the following files on the client in the Windows\System32 directory:

- JNPRCredProv.dll
- JNPRHvExt.dll
- JNPRSmartCardProv.dll
- odGinaLibrary64.dll

### ***Odyssey Access Client on Windows Vista 64-bit***

In Windows Vista (64-bit), the Odyssey Access Client installs the following files on the client in the Windows\SysWOW64 directory:

- odGinaLibrary.dll
- odSendPacket.dll

### ***Odyssey Access Client on Windows Vista 64-bit***

In Windows Vista (64-bit), the Odyssey Access Client installs the following files on the client in the Windows\winsxs\amd64\_microsoft.vc80.crt\_1fc8b3b9a1e18e3b\_8.0.50727.76\_2\_none\_c905be8887838ff2 directory:

- amd64\_Microsoft.VC80.CRT\_1fc8b3b9a1e18e3b\_8.0.50727.762\_x-ww\_9d1c6ce0.cat
- amd64\_Microsoft.VC80.CRT\_1fc8b3b9a1e18e3b\_8.0.50727.762\_x-ww\_9d1c6ce0.manifest
- msvc80.dll
- msvcp80.dll
- msvcr80.dll

### **Odyssey Access Client on Windows Vista 64-bit**

In Windows Vista (64-bit), the Odyssey Access Client installs the following files on the client in the Windows\winsxs\amd64\_policy.8.0.microsoft.vc80.crt\_1fc8b3b9a1e18e3b\_8.0.50727.762\_none\_49e66f4952a1b53b directory:

- 8.0.50727.762.cat
- 8.0.50727.762.policy

### **Odyssey Access Client on Windows Vista 64-bit Registry modifications**

The following modifications to Windows 64-bit include:

[HKEY\_CLASSES\_ROOT\DcfDOM.DomFactory]

@ = "DomFactory Class"

[HKEY\_CLASSES\_ROOT\DcfDOM.DomFactory\CLSID]

@ = "{99DD0F0F-FA5F-11D2-8F6B-008029ED5244}"

[HKEY\_CLASSES\_ROOT\DcfDOM.DomFactory\CurVer]

@ = "DcfDOM.DomFactory.1"

[HKEY\_CLASSES\_ROOT\DcfDOM.DomFactory.1]

@ = "DomFactory Class"

[HKEY\_CLASSES\_ROOT\DcfDOM.DomFactory.1\CLSID]

@ = "{99DD0F0F-FA5F-11D2-8F6B-008029ED5244}"

[HKEY\_CLASSES\_ROOT\OdCert\_M.OdCertLib]

@ = "OdCertLib Class"

[HKEY\_CLASSES\_ROOT\OdCert\_M.OdCertLib\CLSID]

@ = "{D5639173-6BDA-4EA9-85A3-2F1771F4756F}"

```
[HKEY_CLASSES_ROOT\OdCert_M.OdCertLib\CurVer]
@ = "OdCert_M.OdCertLib.1"

[HKEY_CLASSES_ROOT\OdCert_M.OdCertLib.1]
@ = "OdCertLib Class"

[HKEY_CLASSES_ROOT\OdCert_M.OdCertLib.1\CLSID]
@ = "{D5639173-6BDA-4EA9-85A3-2F1771F4756F}"

[HKEY_CLASSES_ROOT\OdClientControl.OdClientConfigurationDatabase]
@ = "OdClientConfigurationDatabase Class"

[HKEY_CLASSES_ROOT\OdClientControl.OdClientConfigurationDatabase\CLSID]
@ = "{CF890798-FED6-49D3-A1F5-947BD485CC03}"

[HKEY_CLASSES_ROOT\OdClientControl.OdClientConfigurationDatabase\CurVer]
@ = "OdClientControl.OdClientConfigurationDatabase.1"

[HKEY_CLASSES_ROOT\OdClientControl.OdClientConfigurationDatabase.1]
@ = "OdClientConfigurationDatabase Class"

[HKEY_CLASSES_ROOT\OdClientControl.OdClientConfigurationDatabase.1\CLSID]
@ = "{CF890798-FED6-49D3-A1F5-947BD485CC03}"

[HKEY_CLASSES_ROOT\OdClientControl.OdClientEngine]
@ = "OdClientEngine Class"

[HKEY_CLASSES_ROOT\OdClientControl.OdClientEngine\CLSID]
@ = "{0A3937EA-5A82-4363-A0CD-4245773C282C}"

[HKEY_CLASSES_ROOT\OdClientControl.OdClientEngine\CurVer]
@ = "OdClientControl.OdClientEngine.1"

[HKEY_CLASSES_ROOT\OdClientControl.OdClientEngine.1]
@ = "OdClientEngine Class"

[HKEY_CLASSES_ROOT\OdClientControl.OdClientEngine.1\CLSID]
@ = "{0A3937EA-5A82-4363-A0CD-4245773C282C}"

[HKEY_CLASSES_ROOT\OdClientControl.OdClientSecurityDatabase]
@ = "OdClientSecurityDatabase Class"
```

[HKEY\_CLASSES\_ROOT\OdClientControl.OdClientSecurityDatabase\CLSID]

@ = "{F24A7852-937D-4D9D-9086-8B976FE979E8}"

[HKEY\_CLASSES\_ROOT\OdClientControl.OdClientSecurityDatabase\CurVer]

@ = "OdClientControl.OdClientSecurityDatabase.1"

[HKEY\_CLASSES\_ROOT\OdClientControl.OdClientSecurityDatabase.1]

@ = "OdClientSecurityDatabase Class"

[HKEY\_CLASSES\_ROOT\OdClientControl.OdClientSecurityDatabase.1\CLSID]

@ = "{F24A7852-937D-4D9D-9086-8B976FE979E8}"

[HKEY\_CLASSES\_ROOT\odClientMgrDialogs.ConfigUI]

@ = "ConfigUI Class"

[HKEY\_CLASSES\_ROOT\odClientMgrDialogs.ConfigUI\CLSID]

@ = "{473D6B6A-AA07-4098-8546-1A15D020F9EE}"

[HKEY\_CLASSES\_ROOT\odClientMgrDialogs.ConfigUI\CurVer]

@ = "odClientMgrDialogs.ConfigUI.1"

[HKEY\_CLASSES\_ROOT\odClientMgrDialogs.ConfigUI.1]

@ = "ConfigUI Class"

[HKEY\_CLASSES\_ROOT\odClientMgrDialogs.ConfigUI.1\CLSID]

@ = "{473D6B6A-AA07-4098-8546-1A15D020F9EE}"

[HKEY\_CLASSES\_ROOT\OdClientService.OdysseyClientService]

@ = "OdysseyClientService Class"

[HKEY\_CLASSES\_ROOT\OdClientService.OdysseyClientService\CLSID]

@ = "{52E64D2C-C33D-42ED-8C82-1EB83CFD9C4E}"

[HKEY\_CLASSES\_ROOT\OdClientService.OdysseyClientService\CurVer]

@ = "OdClientService.OdysseyClientService.1"

[HKEY\_CLASSES\_ROOT\OdClientService.OdysseyClientService.1]

@ = "OdysseyClientService Class"

[HKEY\_CLASSES\_ROOT\OdClientService.OdysseyClientService.1\CLSID]

@ = "{52E64D2C-C33D-42ED-8C82-1EB83CFD9C4E}"

```
[HKEY_CLASSES_ROOT\OdClientService.OdysseyServiceSupplicantMgr]
@ = "OdysseyServiceSupplicantMgr Class"

[HKEY_CLASSES_ROOT\OdClientService.OdysseyServiceSupplicantMgr\CLSID]
@ = "{801B616C-A8CE-4EDC-A7F0-AFE343D44A77}"

[HKEY_CLASSES_ROOT\OdClientService.OdysseyServiceSupplicantMgr\CurVer]
@ = "OdClientService.OdysseyServiceSupplicantMgr.1"

[HKEY_CLASSES_ROOT\OdClientService.OdysseyServiceSupplicantMgr.1]
@ = "OdysseyServiceSupplicantMgr Class"

[HKEY_CLASSES_ROOT\OdClientService.OdysseyServiceSupplicantMgr.1\CLSID]
@ = "{801B616C-A8CE-4EDC-A7F0-AFE343D44A77}"

[HKEY_CLASSES_ROOT\OdConsole.OdConsoleDialog]
@ = "OdConsoleDialog Class"

[HKEY_CLASSES_ROOT\OdConsole.OdConsoleDialog\CLSID]
@ = "{6B891951-71B6-405E-B9E8-3250FCF4BC51}"

[HKEY_CLASSES_ROOT\OdConsole.OdConsoleDialog\CurVer]
@ = "OdConsole.OdConsoleDialog.1"

[HKEY_CLASSES_ROOT\OdConsole.OdConsoleDialog.1]
@ = "OdConsoleDialog Class"

[HKEY_CLASSES_ROOT\OdConsole.OdConsoleDialog.1\CLSID]
@ = "{6B891951-71B6-405E-B9E8-3250FCF4BC51}"

[HKEY_CLASSES_ROOT\OdConsole.OdConsoleLogStream]
@ = "OdConsoleLogStream Class"

[HKEY_CLASSES_ROOT\OdConsole.OdConsoleLogStream\CLSID]
@ = "{CBBFB98A-CC29-440E-A62F-ADD5C69D25DC}"

[HKEY_CLASSES_ROOT\OdConsole.OdConsoleLogStream\CurVer]
@ = "OdConsole.OdConsoleLogStream.1"

[HKEY_CLASSES_ROOT\OdConsole.OdConsoleLogStream.1]
@ = "OdConsoleLogStream Class"
```

[HKEY\_CLASSES\_ROOT\OdConsole.OdConsoleLogStream.1\CLSID]

@ = "{CBBFB98A-CC29-440E-A62F-ADD5C69D25DC}"

[HKEY\_CLASSES\_ROOT\Odjpaservice.odAgentManager]

@ = "odAgentManager Class"

[HKEY\_CLASSES\_ROOT\Odjpaservice.odAgentManager\CLSID]

@ = "{083FC947-9EB1-42AF-8D97-07250E139585}"

[HKEY\_CLASSES\_ROOT\Odjpaservice.odAgentManager\CurVer]

@ = "Odjpaservice.odAgentManager.1"

[HKEY\_CLASSES\_ROOT\Odjpaservice.odAgentManager.1]

@ = "odAgentManager Class"

[HKEY\_CLASSES\_ROOT\Odjpaservice.odAgentManager.1\CLSID]

@ = "{083FC947-9EB1-42AF-8D97-07250E139585}"

[HKEY\_CLASSES\_ROOT\Odjpaservice.odCBConfig]

@ = "odCBConfig Class"

[HKEY\_CLASSES\_ROOT\Odjpaservice.odCBConfig\CLSID]

@ = "{15691C1F-702D-467A-86DC-F527C5F0D615}"

[HKEY\_CLASSES\_ROOT\Odjpaservice.odCBConfig.1]

@ = "odCBConfig Class"

[HKEY\_CLASSES\_ROOT\Odjpaservice.odCBConfig.1\CLSID]

@ = "{15691C1F-702D-467A-86DC-F527C5F0D615}"

[HKEY\_CLASSES\_ROOT\Odjpaservice.odCBMgr]

@ = "odCBMgr Class"

[HKEY\_CLASSES\_ROOT\Odjpaservice.odCBMgr\CLSID]

@ = "{E5A1613D-7813-4FEA-8FB3-850C7DECE9C5}"

[HKEY\_CLASSES\_ROOT\Odjpaservice.odCBMgr.1]

@ = "odCBMgr Class"

[HKEY\_CLASSES\_ROOT\Odjpaservice.odCBMgr.1\CLSID]

@ = "{E5A1613D-7813-4FEA-8FB3-850C7DECE9C5}"

```

[HKEY_CLASSES_ROOT\Odjpaservice.odIPSecConfig]
@ = "odIPSecConfig Class"
[HKEY_CLASSES_ROOT\Odjpaservice.odIPSecConfig\CLSID]
@ = "{5DD07C6B-9CE7-4C86-9784-439F52158448}"
[HKEY_CLASSES_ROOT\Odjpaservice.odIPSecConfig.1]
@ = "odIPSecConfig Class"
[HKEY_CLASSES_ROOT\Odjpaservice.odIPSecConfig.1\CLSID]
@ = "{5DD07C6B-9CE7-4C86-9784-439F52158448}"
[HKEY_CLASSES_ROOT\Odjpaservice.odIPSecMgr]
@ = "odIPSecMgr Class"
[HKEY_CLASSES_ROOT\Odjpaservice.odIPSecMgr\CLSID]
@ = "{BD15F01E-D575-42C9-8E88-C331391FDFA6}"
[HKEY_CLASSES_ROOT\Odjpaservice.odIPSecMgr.1]
@ = "odIPSecMgr Class"
[HKEY_CLASSES_ROOT\Odjpaservice.odIPSecMgr.1\CLSID]
@ = "{BD15F01E-D575-42C9-8E88-C331391FDFA6}"
[HKEY_CLASSES_ROOT\Odjpaservice.odIPSecRoute]
@ = "odIPSecRoute Class"
[HKEY_CLASSES_ROOT\Odjpaservice.odIPSecRoute\CLSID]
@ = "{749EDDC6-1AED-418C-A49C-0B5E67AF8A27}"
[HKEY_CLASSES_ROOT\Odjpaservice.odIPSecRoute.1]
@ = "odIPSecRoute Class"
[HKEY_CLASSES_ROOT\Odjpaservice.odIPSecRoute.1\CLSID]
@ = "{749EDDC6-1AED-418C-A49C-0B5E67AF8A27}"
[HKEY_CLASSES_ROOT\Odjpaservice.OdJuniperSetup]
@ = "OdJuniperSetup Class"
[HKEY_CLASSES_ROOT\Odjpaservice.OdJuniperSetup\CLSID]
@ = "{B911D855-FC84-4192-B0AF-B53CBAB83F54}"

```

```

[HKEY_CLASSES_ROOT\Odjpaservice.OdJuniperSetup\CurVer]
@ = "Odjpaservice.OdJuniperSetup.1"

[HKEY_CLASSES_ROOT\Odjpaservice.OdJuniperSetup.1]
@ = "OdJuniperSetup Class"

[HKEY_CLASSES_ROOT\Odjpaservice.OdJuniperSetup.1\CLSID]
@ = "{B911D855-FC84-4192-B0AF-B53CBAB83F54}"

[HKEY_CLASSES_ROOT\odjpaservice.OdMiniUnZip]
@ = "OdMiniUnZip Class"

[HKEY_CLASSES_ROOT\odjpaservice.OdMiniUnZip\CLSID]
@ = "{DF7A8815-F320-48ED-A219-DAAFB3C1FBD1}"

[HKEY_CLASSES_ROOT\odjpaservice.OdMiniUnZip\CurVer]
@ = "odjpaservice.OdMiniUnZip.1"

[HKEY_CLASSES_ROOT\odjpaservice.OdMiniUnZip.1]
@ = "OdMiniUnZip Class"

[HKEY_CLASSES_ROOT\odjpaservice.OdMiniUnZip.1\CLSID]
@ = "{DF7A8815-F320-48ED-A219-DAAFB3C1FBD1}"

[HKEY_CLASSES_ROOT\Odjpaservice.OdMiniZip]
@ = "OdMiniZip Class"

[HKEY_CLASSES_ROOT\Odjpaservice.OdMiniZip\CLSID]
@ = "{0462122E-567A-48D1-B585-A851C120537D}"

[HKEY_CLASSES_ROOT\Odjpaservice.OdMiniZip\CurVer]
@ = "Odjpaservice.OdMiniZip.1"

[HKEY_CLASSES_ROOT\Odjpaservice.OdMiniZip.1]
@ = "OdMiniZip Class"

[HKEY_CLASSES_ROOT\Odjpaservice.OdMiniZip.1\CLSID]
@ = "{0462122E-567A-48D1-B585-A851C120537D}"

[HKEY_CLASSES_ROOT\Odjpaservice.odSSLSession]
@ = "odSSLSession Class"

```

```
[HKEY_CLASSES_ROOT\Odjpaservice.odSSLSession\CLSID]
@ = "{4E5CA46B-FB17-4EC4-A676-0DD15230863D}"

[HKEY_CLASSES_ROOT\Odjpaservice.odSSLSession.1]
@ = "odSSLSession Class"

[HKEY_CLASSES_ROOT\Odjpaservice.odSSLSession.1\CLSID]
@ = "{4E5CA46B-FB17-4EC4-A676-0DD15230863D}"

[HKEY_CLASSES_ROOT\OdSCard.OdysseyAvailableSCardsFactory]
@ = "OdysseyAvailableSCardsFactory Class"

[HKEY_CLASSES_ROOT\OdSCard.OdysseyAvailableSCardsFactory\CLSID]
@ = "{03104BE6-BDDE-4FC3-B52B-869836FB408F}"

[HKEY_CLASSES_ROOT\OdSCard.OdysseyAvailableSCardsFactory\CurVer]
@ = "OdSCard.OdysseyAvailableSCardsFactory.1"

[HKEY_CLASSES_ROOT\OdSCard.OdysseyAvailableSCardsFactory.1]
@ = "OdysseyAvailableSCardsFactory Class"

[HKEY_CLASSES_ROOT\OdSCard.OdysseyAvailableSCardsFactory.1\CLSID]
@ = "{03104BE6-BDDE-4FC3-B52B-869836FB408F}"

[HKEY_CLASSES_ROOT\OdService.OdysseyEngine]
@ = "OdysseyEngine Class"

[HKEY_CLASSES_ROOT\OdService.OdysseyEngine\CLSID]
@ = "{C4BB5277-BC02-4DE6-846F-E18A50095DF6}"

[HKEY_CLASSES_ROOT\OdService.OdysseyEngine\CurVer]
@ = "OdService.OdysseyEngine.1"

[HKEY_CLASSES_ROOT\OdService.OdysseyEngine.1]
@ = "OdysseyEngine Class"

[HKEY_CLASSES_ROOT\OdService.OdysseyEngine.1\CLSID]
@ = "{C4BB5277-BC02-4DE6-846F-E18A50095DF6}"

[HKEY_CLASSES_ROOT\OdServiceDialogs.OdServiceDialogMgr]
@ = "OdServiceDialogMgr Class"
```

```

[HKEY_CLASSES_ROOT\OdServiceDialogs.OdServiceDialogMgr\CLSID]
@ = "{71486BF6-30BD-4D9B-AD24-3AF8854B7D1E}"

[HKEY_CLASSES_ROOT\OdServiceDialogs.OdServiceDialogMgr\CurVer]
@ = "OdServiceDialogs.OdServiceDialogMgr.1"

[HKEY_CLASSES_ROOT\OdServiceDialogs.OdServiceDialogMgr.1]
@ = "OdServiceDialogMgr Class"

[HKEY_CLASSES_ROOT\OdServiceDialogs.OdServiceDialogMgr.1\CLSID]
@ = "{71486BF6-30BD-4D9B-AD24-3AF8854B7D1E}"

[HKEY_CLASSES_ROOT\OdTnccService.OdTnccStub_Nar]
@ = "OdTnccStub_Nar Class"

[HKEY_CLASSES_ROOT\OdTnccService.OdTnccStub_Nar\CLSID]
@ = "{851F3E86-02D3-4388-84B7-8CC0C3104BB7}"

[HKEY_CLASSES_ROOT\OdTnccService.OdTnccStub_Nar\CurVer]
@ = "OdTnccService.OdTnccStub_Nar.1"

[HKEY_CLASSES_ROOT\OdTnccService.OdTnccStub_Nar.1]
@ = "OdTnccStub_Nar Class"

[HKEY_CLASSES_ROOT\OdTnccService.OdTnccStub_Nar.1\CLSID]
@ = "{851F3E86-02D3-4388-84B7-8CC0C3104BB7}"

[HKEY_CLASSES_ROOT\OdyNWLgxCtl.WirelessTab]
@ = "WirelessTab Class"

[HKEY_CLASSES_ROOT\OdyNWLgxCtl.WirelessTab\CLSID]
@ = "{28321A90-93A8-436A-BD0C-E25E11BB71F1}"

[HKEY_CLASSES_ROOT\OdyNWLgxCtl.WirelessTab\CurVer]
@ = "OdyNWLgxCtl.WirelessTab.1"

[HKEY_CLASSES_ROOT\OdyNWLgxCtl.WirelessTab.1]
@ = "WirelessTab Class"

[HKEY_CLASSES_ROOT\OdyNWLgxCtl.WirelessTab.1\CLSID]
@ = "{28321A90-93A8-436A-BD0C-E25E11BB71F1}"

```

[HKEY\_CLASSES\_ROOT\TypeLib\{17689671-9839-463D-9DAC-2800AA4D74F5}]

[HKEY\_CLASSES\_ROOT\TypeLib\{17689671-9839-463D-9DAC-2800AA4D74F5}\1.0]

@ = "odClientControl 1.0 Type Library"

[HKEY\_CLASSES\_ROOT\TypeLib\{17689671-9839-463D-9DAC-2800AA4D74F5}\1.0\0]

[HKEY\_CLASSES\_ROOT\TypeLib\{17689671-9839-463D-9DAC-2800AA4D74F5}\1.0\0\win32]

@ = "C:\Program Files (x86)\Juniper Networks\Odyssey Access Client\odClientControl.dll"

[HKEY\_CLASSES\_ROOT\TypeLib\{17689671-9839-463D-9DAC-2800AA4D74F5}\1.0\FLAGS]

@ = "0"

[HKEY\_CLASSES\_ROOT\TypeLib\{17689671-9839-463D-9DAC-2800AA4D74F5}\1.0\HELPDIR]

@ = ""

[HKEY\_CLASSES\_ROOT\TypeLib\{2CC76071-B27F-49F1-9C3C-237DD3461A70}]

[HKEY\_CLASSES\_ROOT\TypeLib\{2CC76071-B27F-49F1-9C3C-237DD3461A70}\1.0]

@ = "odServiceDialogs 1.0 Type Library"

[HKEY\_CLASSES\_ROOT\TypeLib\{2CC76071-B27F-49F1-9C3C-237DD3461A70}\1.0\0]

[HKEY\_CLASSES\_ROOT\TypeLib\{2CC76071-B27F-49F1-9C3C-237DD3461A70}\1.0\0\win32]

@ = "C:\Program Files (x86)\Juniper Networks\Odyssey Access Client\odServiceDialogs.dll"

[HKEY\_CLASSES\_ROOT\TypeLib\{2CC76071-B27F-49F1-9C3C-237DD3461A70}\1.0\FLAGS]

@ = "0"

[HKEY\_CLASSES\_ROOT\TypeLib\{2CC76071-B27F-49F1-9C3C-237DD3461A70}\1.0\HELPDIR]

@ = ""

[HKEY\_CLASSES\_ROOT\TypeLib\{3880EABE-2031-47EA-8BB7-8E9709A41D7A}]

```
[HKEY_CLASSES_ROOT\TypeLib\{3880EABE-2031-47EA-8BB7-8E9709A41D7A}\1.0]
```

```
@ = "odSCard 1.0 Type Library"
```

```
[HKEY_CLASSES_ROOT\TypeLib\{3880EABE-2031-47EA-8BB7-8E9709A41D7A}\1.0\0]
```

```
[HKEY_CLASSES_ROOT\TypeLib\{3880EABE-2031-47EA-8BB7-8E9709A41D7A}\1.0\0\win32]
```

```
@ = "C:\Program Files (x86)\Juniper Networks\Odyssey Access Client\odSCard.dll"
```

```
[HKEY_CLASSES_ROOT\TypeLib\{3880EABE-2031-47EA-8BB7-8E9709A41D7A}\1.0\FLAGS]
```

```
@ = "0"
```

```
[HKEY_CLASSES_ROOT\TypeLib\{3880EABE-2031-47EA-8BB7-8E9709A41D7A}\1.0\HELPPDIR]
```

```
@ = ""
```

```
[HKEY_CLASSES_ROOT\TypeLib\{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}]
```

```
[HKEY_CLASSES_ROOT\TypeLib\{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}\1.0]
```

```
@ = "odService 1.0 Type Library"
```

```
[HKEY_CLASSES_ROOT\TypeLib\{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}\1.0\0]
```

```
[HKEY_CLASSES_ROOT\TypeLib\{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}\1.0\0\win32]
```

```
@ = "C:\Program Files (x86)\Juniper Networks\Odyssey Access Client\odService.dll"
```

```
[HKEY_CLASSES_ROOT\TypeLib\{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}\1.0\FLAGS]
```

```
@ = "0"
```

```
[HKEY_CLASSES_ROOT\TypeLib\{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}\1.0\HELPPDIR]
```

```
@ = ""
```

```
[HKEY_CLASSES_ROOT\TypeLib\{9CDEA2D2-AD17-4BA7-9E69-CDA395508EDD}]
```

```
[HKEY_CLASSES_ROOT\TypeLib\{9CDEA2D2-AD17-4BA7-9E69-CDA395508EDD}\1.0]
```

@ = "odjpaservice 1.0 Type Library"

[HKEY\_CLASSES\_ROOT\TypeLib\{9CDEA2D2-AD17-4BA7-9E69-CDA395508EDD}\1.0\0]

[HKEY\_CLASSES\_ROOT\TypeLib\{9CDEA2D2-AD17-4BA7-9E69-CDA395508EDD}\1.0\0\win32]

@ = "C:\Program Files (x86)\Juniper Networks\Odyssey Access Client\odjpaservice.dll"

[HKEY\_CLASSES\_ROOT\TypeLib\{9CDEA2D2-AD17-4BA7-9E69-CDA395508EDD}\1.0\FLAGS]

@ = "0"

[HKEY\_CLASSES\_ROOT\TypeLib\{9CDEA2D2-AD17-4BA7-9E69-CDA395508EDD}\1.0\HELPDIR]

@ = ""

[HKEY\_CLASSES\_ROOT\TypeLib\{D949A4C7-7F76-4052-A2D3-F3C40BE7ABE5}]

[HKEY\_CLASSES\_ROOT\TypeLib\{D949A4C7-7F76-4052-A2D3-F3C40BE7ABE5}\1.0]

@ = "odClientService 1.0 Type Library"

[HKEY\_CLASSES\_ROOT\TypeLib\{D949A4C7-7F76-4052-A2D3-F3C40BE7ABE5}\1.0\0]

[HKEY\_CLASSES\_ROOT\TypeLib\{D949A4C7-7F76-4052-A2D3-F3C40BE7ABE5}\1.0\0\win32]

@ = "C:\Program Files (x86)\Juniper Networks\Odyssey Access Client\odClientService.exe"

[HKEY\_CLASSES\_ROOT\TypeLib\{D949A4C7-7F76-4052-A2D3-F3C40BE7ABE5}\1.0\FLAGS]

@ = "0"

[HKEY\_CLASSES\_ROOT\TypeLib\{D949A4C7-7F76-4052-A2D3-F3C40BE7ABE5}\1.0\HELPDIR]

@ = ""

[HKEY\_CLASSES\_ROOT\TypeLib\{EDA6503C-E7A9-4BD0-9A2A-79466C41FF88}]

[HKEY\_CLASSES\_ROOT\TypeLib\{EDA6503C-E7A9-4BD0-9A2A-79466C41FF88}\1.0]

@ = "odcConfigUI 1.0 Type Library"

[HKEY\_CLASSES\_ROOT\TypeLib\{EDA6503C-E7A9-4BD0-9A2A-79466C41FF88}\1.0\0]

[HKEY\_CLASSES\_ROOT\TypeLib\{EDA6503C-E7A9-4BD0-9A2A-79466C41FF88}\1.0\0\win32]

@ = "C:\Program Files (x86)\Juniper Networks\Odyssey Access Client\odClientMgrDialogs.dll"

[HKEY\_CLASSES\_ROOT\TypeLib\{EDA6503C-E7A9-4BD0-9A2A-79466C41FF88}\1.0\FLAGS]

@ = "0"

[HKEY\_CLASSES\_ROOT\TypeLib\{EDA6503C-E7A9-4BD0-9A2A-79466C41FF88}\1.0\HELPPDIR]

@ = ""

[HKEY\_CLASSES\_ROOT\TypeLib\{FFC6CC98-F00D-44E3-9B33-40B442258468}]

[HKEY\_CLASSES\_ROOT\TypeLib\{FFC6CC98-F00D-44E3-9B33-40B442258468}\1.0]

@ = "odyNWLgxCtl 1.0 Type Library"

[HKEY\_CLASSES\_ROOT\TypeLib\{FFC6CC98-F00D-44E3-9B33-40B442258468}\1.0\0]

[HKEY\_CLASSES\_ROOT\TypeLib\{FFC6CC98-F00D-44E3-9B33-40B442258468}\1.0\0\win32]

@ = "C:\Program Files (x86)\Juniper Networks\Odyssey Access Client\odyNwLgXctl.ocx"

[HKEY\_CLASSES\_ROOT\TypeLib\{FFC6CC98-F00D-44E3-9B33-40B442258468}\1.0\FLAGS]

@ = "0"

[HKEY\_CLASSES\_ROOT\TypeLib\{FFC6CC98-F00D-44E3-9B33-40B442258468}\1.0\HELPPDIR]

@ = ""

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{0462122E-567A-48D1-B585-A851C120537D}]

@ = "OdMiniZip Class"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{0462122E-567A-48D1-B585-A851C120537D}\InprocServer32]

@ = "C:\Program Files (x86)\Juniper Networks\Odyssey Access Client\odjpaservice.dll"

"ThreadingModel" = "Apartment"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{0462122E-567A-48D1-B585-A851C120537D}\ProgID]

@ = "Odjpaservice.OdMiniZip.1"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{0462122E-567A-48D1-B585-A851C120537D}\TypeLib]

@ = "{9CDEA2D2-AD17-4BA7-9E69-CDA395508EDD}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{0462122E-567A-48D1-B585-A851C120537D}\VersionIndependentProgID]

@ = "Odjpaservice.OdMiniZip"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{083FC947-9EB1-42AF-8D97-07250E139585}]

@ = "odAgentManager Class"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{083FC947-9EB1-42AF-8D97-07250E139585}\InprocServer32]

@ = "C:\Program Files (x86)\Juniper Networks\Odyssey Access Client\odjpaservice.dll"

"ThreadingModel" = "Free"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{083FC947-9EB1-42AF-8D97-07250E139585}\ProgID]

@ = "Odjpaservice.odAgentManager.1"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{083FC947-9EB1-42AF-8D97-07250E139585}\Programmable]

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{083FC947-9EB1-42AF-8D97-07250E139585}\TypeLib]

@ = "{9CDEA2D2-AD17-4BA7-9E69-CDA395508EDD}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{083FC947-9EB1-42AF-8D97-07250E139585}\VersionIndependentProgID]

@ = "Odjpaservice.odAgentManager"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{0A3937EA-5A82-4363-A0CD-4245773C282C}]

@ = "OdClientEngine Class"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{0A3937EA-5A82-4363-A0CD-4245773C282C}\InprocServer32]

@ = "C:\Program Files (x86)\Juniper Networks\Odyssey Access Client\odClientControl.dll"

"ThreadingModel" = "Both"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{0A3937EA-5A82-4363-A0CD-4245773C282C}\ProgID]

@ = "OdClientControl.OdClientEngine.1"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{0A3937EA-5A82-4363-A0CD-4245773C282C}\Programmable]

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{0A3937EA-5A82-4363-A0CD-4245773C282C}\TypeLib]

@ = "{17689671-9839-463D-9DAC-2800AA4D74F5}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{0A3937EA-5A82-4363-A0CD-4245773C282C}\VersionIndependentProgID]

@ = "OdClientControl.OdClientEngine"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{15691C1F-702D-467A-86DC-F527C5F0D615}]

@ = "odCBConfig Class"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{15691C1F-702D-467A-86DC-F527C5F0D615}\InprocServer32]

@ = "C:\Program Files (x86)\Juniper Networks\Odyssey Access Client\odjpaservice.dll"

"ThreadingModel" = "both"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{15691C1F-702D-467A-86DC-F527C5F0D615}\ProgID]

@ = "Odjpaservice.odCBConfig.1"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{15691C1F-702D-467A-86DC-F527C5F0D615}\VersionIndependentProgID]

@ = "Odjpaservice.odCBConfig"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{DF7A8815-F320-48ED-A219-DAAFB3C1FBD1}]

@ = "OdMiniUnZip Class"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{DF7A8815-F320-48ED-A219-DAAFB3C1FBD1}\InprocServer32]

@ = "C:\Program Files (x86)\Juniper Networks\Odyssey Access Client\odjpaservice.dll"

"ThreadingModel" = "Apartment"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{DF7A8815-F320-48ED-A219-DAAFB3C1FBD1}\ProgID]

@ = "odjpaservice.OdMiniUnZip.1"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{DF7A8815-F320-48ED-A219-DAAFB3C1FBD1}\Programmable]

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{DF7A8815-F320-48ED-A219-DAAFB3C1FBD1}\TypeLib]

@ = "{}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{DF7A8815-F320-48ED-A219-DAAFB3C1FBD1}\VersionIndependentProgID]

@ = "odjpaservice.OdMiniUnZip"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{E5A1613D-7813-4FEA-8FB3-850C7DECE9C5}]

@ = "odCBMgr Class"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{E5A1613D-7813-4FEA-8FB3-850C7DECE9C5}\InprocServer32]

@ = "C:\Program Files (x86)\Juniper Networks\Odyssey Access Client\odjpaservice.dll"

"ThreadingModel" = "both"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{E5A1613D-7813-4FEA-8FB3-850C7DECE9C5}\ProgID]

@ = "Odjpaservice.odCBMgr.1"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{E5A1613D-7813-4FEA-8FB3-850C7DECE9C5}\VersionIndependentProgID]

@ = "Odjpaservice.odCBMgr"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{F24A7852-937D-4D9D-9086-8B976FE979E8}]

@ = "OdClientSecurityDatabase Class"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{F24A7852-937D-4D9D-9086-8B976FE979E8}\InprocServer32]

@ = "C:\Program Files (x86)\Juniper Networks\Odyssey Access Client\OdClientControl.dll"

"ThreadingModel" = "Both"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{F24A7852-937D-4D9D-9086-8B976FE979E8}\ProgID]

@ = "OdClientControl.OdClientSecurityDatabase.1"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{F24A7852-937D-4D9D-9086-8B976FE979E8}\Programmable]

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{F24A7852-937D-4D9D-9086-8B976FE979E8}\TypeLib]

@ = "{17689671-9839-463D-9DAC-2800AA4D74F5}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\CLSID\{F24A7852-937D-4D9D-9086-8B976FE979E8}\VersionIndependentProgID]

@ = "OdClientControl.OdClientSecurityDatabase"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{00FAB823-2BBF-4A96-A397-AA2863F7215B}]

@ = "IOdysseySupplicantStatus"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{00FAB823-2BBF-4A96-A397-AA2863F7215B}\ProxyStubClsid]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{00FAB823-2BBF-4A96-A397-AA2863F7215B}\ProxyStubClsid32]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{00FAB823-2BBF-4A96-A397-AA2863F7215B}\TypeLib]

@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"

"Version" = "1.0"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{13F6B17E-7057-4860-BBB2-4180A5EA4854}]

@ = "IOdysseySupplicantStatistics"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{13F6B17E-7057-4860-BBB2-4180A5EA4854}\ProxyStubClsid]

@ = "{00020424-0000-0000-C000-000000000046}"

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{13F6B17E-7057-4860-BBB2-4180A5EA4854}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{13F6B17E-7057-4860-BBB2-4180A5EA4854}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{2046CC8A-A639-4BB0-9DCD-AF9BFC85EE41}]
```

```
@ = "IOdysseyIC"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{2046CC8A-A639-4BB0-9DCD-AF9BFC85EE41}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{2046CC8A-A639-4BB0-9DCD-AF9BFC85EE41}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{2046CC8A-A639-4BB0-9DCD-AF9BFC85EE41}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{20FCF5F9-590D-46ED-89C4-261AB89459CF}]
```

```
@ = "IOdysseySCardLogObserver"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{20FCF5F9-590D-46ED-89C4-261AB89459CF}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{20FCF5F9-590D-46ED-89C4-261AB89459CF}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{20FCF5F9-590D-46ED-89C4-261AB89459CF}\TypeLib]
```

```
@ = "{3880EABE-2031-47EA-8BB7-8E9709A41D7A}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{3ABAD91D-A962-436A-8F18-090DFE37854E}]
```

```
@ = "IOdysseyTunnel"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{3ABAD91D-A962-436A-8F18-090DFE37854E}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{3ABAD91D-A962-436A-8F18-090DFE37854E}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{3ABAD91D-A962-436A-8F18-090DFE37854E}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{3EE4AFC6-0386-4E73-8D7D-74419EE1EBCA}]
```

```
@ = "IOdysseyTunnels"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{3EE4AFC6-0386-4E73-8D7D-74419EE1EBCA}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{3EE4AFC6-0386-4E73-8D7D-74419EE1EBCA}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{3EE4AFC6-0386-4E73-8D7D-74419EE1EBCA}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{42982519-7168-4B1F-9244-7B61E6C23C7E}]
```

```
@ = "IOdysseyProvisionedPac"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{42982519-7168-4B1F-9244-7B61E6C23C7E}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{42982519-7168-4B1F-9244-7B61E6C23C7E}\ProxyStubClsid32]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{42982519-7168-4B1F-9244-7B61E6C23C7E}\TypeLib]

@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"

"Version" = "1.0"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{500782DE-C095-4BD1-9817-86523C9F0716}]

@ = "IOdysseyEngine"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{500782DE-C095-4BD1-9817-86523C9F0716}\ProxyStubClsid]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{500782DE-C095-4BD1-9817-86523C9F0716}\ProxyStubClsid32]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{500782DE-C095-4BD1-9817-86523C9F0716}\TypeLib]

@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"

"Version" = "1.0"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{572FCB98-154C-4FBC-BDA7-8B2A5A27E93D}]

@ = "IOdysseyEventObserver"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{572FCB98-154C-4FBC-BDA7-8B2A5A27E93D}\ProxyStubClsid]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{572FCB98-154C-4FBC-BDA7-8B2A5A27E93D}\ProxyStubClsid32]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{572FCB98-154C-4FBC-BDA7-8B2A5A27E93D}\TypeLib]

@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"

"Version" = "1.0"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{5BB9E8AB-AC6B-4482-AFDE-5A3F394A59B0}]

@ = "IOdysseySupplicantMgr\_NAC"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{5BB9E8AB-AC6B-4482-AFDE-5A3F394A59B0}\ProxyStubClsid]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{5BB9E8AB-AC6B-4482-AFDE-5A3F394A59B0}\ProxyStubClsid32]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{5BB9E8AB-AC6B-4482-AFDE-5A3F394A59B0}\TypeLib]

@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"

"Version" = "1.0"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{63345CF1-4B80-4423-814D-01C810E730CD}]

@ = "\_IOdysseySupplicantMgrEvents"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{63345CF1-4B80-4423-814D-01C810E730CD}\ProxyStubClsid]

@ = "{00020420-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{63345CF1-4B80-4423-814D-01C810E730CD}\ProxyStubClsid32]

@ = "{00020420-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{63345CF1-4B80-4423-814D-01C810E730CD}\TypeLib]

@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"

"Version" = "1.0"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{657310C1-7689-43F4-B6EE-28DE607920F3}]

@ = "IOdysseyTncStatus"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{657310C1-7689-43F4-B6EE-28DE607920F3}\ProxyStubClsid]

@ = "{00020424-0000-0000-C000-000000000046}"

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{657310C1-7689-43F4-B6EE-28DE607920F3}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{657310C1-7689-43F4-B6EE-28DE607920F3}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{65CDC8C4-DAF7-48A4-A84B-2D20F70B4E5F}]
```

```
@ = "IOdysseySupplicantMgrContext"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{65CDC8C4-DAF7-48A4-A84B-2D20F70B4E5F}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{65CDC8C4-DAF7-48A4-A84B-2D20F70B4E5F}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{65CDC8C4-DAF7-48A4-A84B-2D20F70B4E5F}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{6679A8B3-B560-4441-A6CE-B516667D59CC}]
```

```
@ = "IOdysseyBSSIDs"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{6679A8B3-B560-4441-A6CE-B516667D59CC}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{6679A8B3-B560-4441-A6CE-B516667D59CC}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{6679A8B3-B560-4441-A6CE-B516667D59CC}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{6AB10DB0-A735-4DAE-8379-
C69AF5BAC0C6}]
```

```
@ = "_IOdysseyICEvents"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{6AB10DB0-A735-4DAE-8379-
C69AF5BAC0C6}\ProxyStubClsid]
```

```
@ = "{00020420-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{6AB10DB0-A735-4DAE-8379-
C69AF5BAC0C6}\ProxyStubClsid32]
```

```
@ = "{00020420-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{6AB10DB0-A735-4DAE-8379-
C69AF5BAC0C6}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{6CCED896-0F91-4D5B-A38D-
84041F787322}]
```

```
@ = "_IOdysseyUACMgrEvents"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{6CCED896-0F91-4D5B-A38D-
84041F787322}\ProxyStubClsid]
```

```
@ = "{00020420-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{6CCED896-0F91-4D5B-A38D-
84041F787322}\ProxyStubClsid32]
```

```
@ = "{00020420-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{6CCED896-0F91-4D5B-A38D-
84041F787322}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{707DD4EA-299C-40D2-829C-
0B9B4863FEC7}]
```

```
@ = "IOdysseyBSSID"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{707DD4EA-299C-40D2-829C-
0B9B4863FEC7}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{707DD4EA-299C-40D2-829C-0B9B4863FEC7}\ProxyStubClsid32]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{707DD4EA-299C-40D2-829C-0B9B4863FEC7}\TypeLib]

@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"

"Verion" = "1.0"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{7BFFFA48-C4E0-469E-A772-B958D2BEAEB1}]

@ = "IOdysseyAvailableSCards"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{7BFFFA48-C4E0-469E-A772-B958D2BEAEB1}\ProxyStubClsid]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{7BFFFA48-C4E0-469E-A772-B958D2BEAEB1}\ProxyStubClsid32]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{7BFFFA48-C4E0-469E-A772-B958D2BEAEB1}\TypeLib]

@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"

"Version" = "1.0"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{7CB08D7A-7E84-4BD8-8436-58305B354A62}]

@ = "IOdysseyTunnelStatus"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{7CB08D7A-7E84-4BD8-8436-58305B354A62}\ProxyStubClsid]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{7CB08D7A-7E84-4BD8-8436-58305B354A62}\ProxyStubClsid32]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{7CB08D7A-7E84-4BD8-8436-58305B354A62}\TypeLib]

@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"

"Version" = "1.0"

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{827E5740-B06E-4A66-855C-2AE3FF8FFC2D}]
```

```
@ = "IOdysseyProvisionedPacs"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{827E5740-B06E-4A66-855C-2AE3FF8FFC2D}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{827E5740-B06E-4A66-855C-2AE3FF8FFC2D}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{827E5740-B06E-4A66-855C-2AE3FF8FFC2D}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{83E52ED1-BA21-4D4C-AB17-65C513390F9B}]
```

```
@ = "IOdysseyClientPlugin"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{83E52ED1-BA21-4D4C-AB17-65C513390F9B}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{83E52ED1-BA21-4D4C-AB17-65C513390F9B}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{83E52ED1-BA21-4D4C-AB17-65C513390F9B}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{87DC252A-3F79-469C-808F-C65C8F0FA800}]
```

```
@ = "IOdysseySCCollection"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{87DC252A-3F79-469C-808F-C65C8F0FA800}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{87DC252A-3F79-469C-808F-C65C8F0FA800}\ProxyStubClsid32]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{87DC252A-3F79-469C-808F-C65C8F0FA800}\TypeLib]

@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"

"Version" = "1.0"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{8AFABAD7-EA05-48B2-B615-F9B8DE14056E}]

@ = "IOdysseyClientPlugins"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{8AFABAD7-EA05-48B2-B615-F9B8DE14056E}\ProxyStubClsid]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{8AFABAD7-EA05-48B2-B615-F9B8DE14056E}\ProxyStubClsid32]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{8AFABAD7-EA05-48B2-B615-F9B8DE14056E}\TypeLib]

@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"

"Version" = "1.0"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{8C1B1268-C810-4CFC-9EED-FEFD4F6BC7FD}]

@ = "\_IOdysseySupplicantEvents"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{8C1B1268-C810-4CFC-9EED-FEFD4F6BC7FD}\ProxyStubClsid]

@ = "{00020420-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{8C1B1268-C810-4CFC-9EED-FEFD4F6BC7FD}\ProxyStubClsid32]

@ = "{00020420-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{8C1B1268-C810-4CFC-9EED-FEFD4F6BC7FD}\TypeLib]

@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"

"Version" = "1.0"

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{8D38CD9F-6AB2-4C60-A6C6-FD052D2610CA}]
```

```
@ = "IOdysseySCardEventObserver"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{8D38CD9F-6AB2-4C60-A6C6-FD052D2610CA}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{8D38CD9F-6AB2-4C60-A6C6-FD052D2610CA}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{8D38CD9F-6AB2-4C60-A6C6-FD052D2610CA}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{9A27F6B5-0C87-4CAA-8225-C0FB7D92FC20}]
```

```
@ = "IOdysseyAuthenticationStatus"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{9A27F6B5-0C87-4CAA-8225-C0FB7D92FC20}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{9A27F6B5-0C87-4CAA-8225-C0FB7D92FC20}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{9A27F6B5-0C87-4CAA-8225-C0FB7D92FC20}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{A5652786-A62D-483F-9F65-C7117E5E2F14}]
```

```
@ = "IOdysseySCard"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{A5652786-A62D-483F-9F65-C7117E5E2F14}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{A5652786-A62D-483F-9F65-C7117E5E2F14}\ProxyStubClsid32]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{A5652786-A62D-483F-9F65-C7117E5E2F14}\TypeLib]

@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"

"Version" = "1.0"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{A8CBF256-1FED-4448-822C-7533CBD7A92E}]

@ = "IOdysseyICStatus"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{A8CBF256-1FED-4448-822C-7533CBD7A92E}\ProxyStubClsid]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{A8CBF256-1FED-4448-822C-7533CBD7A92E}\ProxyStubClsid32]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{A8CBF256-1FED-4448-822C-7533CBD7A92E}\TypeLib]

@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"

"Version" = "1.0"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{BD4302EB-C75B-4FB2-BB8D-AD162CF4397D}]

@ = "IOdysseyUACMgr"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{BD4302EB-C75B-4FB2-BB8D-AD162CF4397D}\ProxyStubClsid]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{BD4302EB-C75B-4FB2-BB8D-AD162CF4397D}\ProxyStubClsid32]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{BD4302EB-C75B-4FB2-BB8D-AD162CF4397D}\TypeLib]

@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"

"Version" = "1.0"

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{C9539895-71E8-4735-B879-D03B21745DB7}]
```

```
@ = "IOdysseyIhvObserver"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{C9539895-71E8-4735-B879-D03B21745DB7}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{C9539895-71E8-4735-B879-D03B21745DB7}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{C9539895-71E8-4735-B879-D03B21745DB7}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{D3379769-0DC4-4A1C-83FD-B0D6A8865ADD}]
```

```
@ = "IOdysseySupplicantMgr"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{D3379769-0DC4-4A1C-83FD-B0D6A8865ADD}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{D3379769-0DC4-4A1C-83FD-B0D6A8865ADD}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{D3379769-0DC4-4A1C-83FD-B0D6A8865ADD}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{E1B0B9EF-BED7-4309-99EC-5B9C531AC4EC}]
```

```
@ = "IOdysseyClientService"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{E1B0B9EF-BED7-4309-99EC-5B9C531AC4EC}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{E1B0B9EF-BED7-4309-99EC-5B9C531AC4EC}\ProxyStubClsid32]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{E1B0B9EF-BED7-4309-99EC-5B9C531AC4EC}\TypeLib]

@ = "{D949A4C7-7F76-4052-A2D3-F3C40BE7ABE5}"

"Version" = "1.0"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{E7908ECC-907D-4787-B272-801E8D07EA70}]

@ = "IOdysseySuplicants"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{E7908ECC-907D-4787-B272-801E8D07EA70}\ProxyStubClsid]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{E7908ECC-907D-4787-B272-801E8D07EA70}\ProxyStubClsid32]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{E7908ECC-907D-4787-B272-801E8D07EA70}\TypeLib]

@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"

"Version" = "1.0"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{F76369AA-BD0E-4209-AB51-68C070C7EB14}]

@ = "IOdysseyAvailableAdapter"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{F76369AA-BD0E-4209-AB51-68C070C7EB14}\ProxyStubClsid]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{F76369AA-BD0E-4209-AB51-68C070C7EB14}\ProxyStubClsid32]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{F76369AA-BD0E-4209-AB51-68C070C7EB14}\TypeLib]

@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"

"Version" = "1.0"

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{F8644E8F-A309-417E-9F0B-64671EBCA1C7}]
```

```
@ = "IOdysseyICs"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{F8644E8F-A309-417E-9F0B-64671EBCA1C7}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{F8644E8F-A309-417E-9F0B-64671EBCA1C7}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{F8644E8F-A309-417E-9F0B-64671EBCA1C7}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{FF981AE5-730B-4357-9CD6-05DA2C9AD327}]
```

```
@ = "IOdysseySupplicant"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{FF981AE5-730B-4357-9CD6-05DA2C9AD327}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{FF981AE5-730B-4357-9CD6-05DA2C9AD327}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{FF981AE5-730B-4357-9CD6-05DA2C9AD327}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{FFF8DAE6-FFC9-4026-A0D3-A03F851598BD}]
```

```
@ = "IOdysseyCollection"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{FFF8DAE6-FFC9-4026-A0D3-A03F851598BD}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{FFF8DAE6-FFC9-4026-A0D3-A03F851598BD}\ProxyStubClsid32]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Interface\{FFF8DAE6-FFC9-4026-A0D3-A03F851598BD}\TypeLib]

@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"

"Version" = "1.0"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdCert\_M.OdCertLib]

@ = "OdCertLib Class"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdCert\_M.OdCertLib\CLSID]

@ = "{D5639173-6BDA-4EA9-85A3-2F1771F4756F}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdCert\_M.OdCertLib\CurVer]

@ = "OdCert\_M.OdCertLib.1"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdCert\_M.OdCertLib.1]

@ = "OdCertLib Class"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdCert\_M.OdCertLib.1\CLSID]

@ = "{D5639173-6BDA-4EA9-85A3-2F1771F4756F}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdClientControl.OdClientConfigurationDatabase]

@ = "OdClientConfigurationDatabase Class"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdClientControl.OdClientConfigurationDatabase\CLSID]

@ = "{CF890798-FED6-49D3-A1F5-947BD485CC03}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdClientControl.OdClientConfigurationDatabase\CurVer]

@ = "OdClientControl.OdClientConfigurationDatabase.1"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdClientControl.OdClientConfigurationDatabase.1]

@ = "OdClientConfigurationDatabase Class"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdClientControl.OdClientConfigurationDatabase.1\CLSID]

@ = "{CF890798-FED6-49D3-A1F5-947BD485CC03}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdClientControl.OdClientEngine]

@ = "OdClientEngine Class"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdClientControl.OdClientEngine\CLSID]

@ = "{0A3937EA-5A82-4363-A0CD-4245773C282C}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdClientControl.OdClientEngine\CurVer]

@ = "OdClientControl.OdClientEngine.1"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdClientControl.OdClientEngine.1]

@ = "OdClientEngine Class"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdClientControl.OdClientEngine.1\CLSID]

@ = "{0A3937EA-5A82-4363-A0CD-4245773C282C}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdClientControl.OdClientSecurityDatabase  
]

@ = "OdClientSecurityDatabase Class"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdClientControl.OdClientSecurityDatabase  
\CLSID]

@ = "{F24A7852-937D-4D9D-9086-8B976FE979E8}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdClientControl.OdClientSecurityDatabase  
\CurVer]

@ = "OdClientControl.OdClientSecurityDatabase.1"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdClientControl.OdClientSecurityDatabase  
.1]

@ = "OdClientSecurityDatabase Class"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdClientControl.OdClientSecurityDatabase  
.1\CLSID]

@ = "{F24A7852-937D-4D9D-9086-8B976FE979E8}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\odClientMgrDialogs.ConfigUI]

@ = "ConfigUI Class"

[HKEY\_CLASSES\_ROOT\Wow6432Node\odClientMgrDialogs.ConfigUI\CLSID]

@ = "{473D6B6A-AA07-4098-8546-1A15D020F9EE}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\odClientMgrDialogs.ConfigUI\CurVer]

```

@ = "odClientMgrDialogs.ConfigUI.1"
[HKEY_CLASSES_ROOT\Wow6432Node\odClientMgrDialogs.ConfigUI.1]

@ = "ConfigUI Class"
[HKEY_CLASSES_ROOT\Wow6432Node\odClientMgrDialogs.ConfigUI.1\CLSID]

@ = "{473D6B6A-AA07-4098-8546-1A15D020F9EE}"
[HKEY_CLASSES_ROOT\Wow6432Node\OdClientService.OdysseyClientService]

@ = "OdysseyClientService Class"
[HKEY_CLASSES_ROOT\Wow6432Node\OdClientService.OdysseyClientService\CLSID]

@ = "{52E64D2C-C33D-42ED-8C82-1EB83CFD9C4E}"
[HKEY_CLASSES_ROOT\Wow6432Node\OdClientService.OdysseyClientService\CurVer]

@ = "OdClientService.OdysseyClientService.1"
[HKEY_CLASSES_ROOT\Wow6432Node\OdClientService.OdysseyClientService.1]

@ = "OdysseyClientService Class"
[HKEY_CLASSES_ROOT\Wow6432Node\OdClientService.OdysseyClientService.1\CLSID]

@ = "{52E64D2C-C33D-42ED-8C82-1EB83CFD9C4E}"
[HKEY_CLASSES_ROOT\Wow6432Node\OdClientService.OdysseyServiceSupplicantMgr]

@ = "OdysseyServiceSupplicantMgr Class"
[HKEY_CLASSES_ROOT\Wow6432Node\OdClientService.OdysseyServiceSupplicantMgr\CLSID]

@ = "{801B616C-A8CE-4EDC-A7F0-AFE343D44A77}"
[HKEY_CLASSES_ROOT\Wow6432Node\OdClientService.OdysseyServiceSupplicantMgr\CurVer]

@ = "OdClientService.OdysseyServiceSupplicantMgr.1"
[HKEY_CLASSES_ROOT\Wow6432Node\OdClientService.OdysseyServiceSupplicantMgr.1]

@ = "OdysseyServiceSupplicantMgr Class"
[HKEY_CLASSES_ROOT\Wow6432Node\OdClientService.OdysseyServiceSupplicantMgr.1\CLSID]

```

@ = "{801B616C-A8CE-4EDC-A7F0-AFE343D44A77}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdConsole.OdConsoleDialog]

@ = "OdConsoleDialog Class"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdConsole.OdConsoleDialog\CLSID]

@ = "{6B891951-71B6-405E-B9E8-3250FCF4BC51}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdConsole.OdConsoleDialog\CurVer]

@ = "OdConsole.OdConsoleDialog.1"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdConsole.OdConsoleDialog.1]

@ = "OdConsoleDialog Class"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdConsole.OdConsoleDialog.1\CLSID]

@ = "{6B891951-71B6-405E-B9E8-3250FCF4BC51}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdConsole.OdConsoleLogStream]

@ = "OdConsoleLogStream Class"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdConsole.OdConsoleLogStream\CLSID]

@ = "{CBBFB98A-CC29-440E-A62F-ADD5C69D25DC}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdConsole.OdConsoleLogStream\CurVer]

@ = "OdConsole.OdConsoleLogStream.1"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdConsole.OdConsoleLogStream.1]

@ = "OdConsoleLogStream Class"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdConsole.OdConsoleLogStream.1\CLSID]

@ = "{CBBFB98A-CC29-440E-A62F-ADD5C69D25DC}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Odjpaservice.odAgentManager]

@ = "odAgentManager Class"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Odjpaservice.odAgentManager\CLSID]

@ = "{083FC947-9EB1-42AF-8D97-07250E139585}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Odjpaservice.odAgentManager\CurVer]

@ = "Odjpaservice.odAgentManager.1"

[HKEY\_CLASSES\_ROOT\Wow6432Node\Odjpaservice.odAgentManager.1]

```

@ = "odAgentManager Class"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.odAgentManager.1\CLSID]
@ = "{083FC947-9EB1-42AF-8D97-07250E139585}"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.odCBConfig]
@ = "odCBConfig Class"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.odCBConfig\CLSID]
@ = "{15691C1F-702D-467A-86DC-F527C5F0D615}"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.odCBConfig.1]
@ = "odCBConfig Class"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.odCBConfig.1\CLSID]
@ = "{15691C1F-702D-467A-86DC-F527C5F0D615}"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.odCBMgr]
@ = "odCBMgr Class"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.odCBMgr\CLSID]
@ = "{E5A1613D-7813-4FEA-8FB3-850C7DECE9C5}"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.odCBMgr.1]
@ = "odCBMgr Class"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.odCBMgr.1\CLSID]
@ = "{E5A1613D-7813-4FEA-8FB3-850C7DECE9C5}"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.odIPSecConfig]
@ = "odIPSecConfig Class"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.odIPSecConfig\CLSID]
@ = "{5DD07C6B-9CE7-4C86-9784-439F52158448}"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.odIPSecConfig.1]
@ = "odIPSecConfig Class"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.odIPSecConfig.1\CLSID]
@ = "{5DD07C6B-9CE7-4C86-9784-439F52158448}"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.odIPSecMgr]

```

```

@ = "odIPSecMgr Class"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.odIPSecMgr\CLSID]
@ = "{BD15F01E-D575-42C9-8E88-C331391FDFA6}"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.odIPSecMgr.1]
@ = "odIPSecMgr Class"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.odIPSecMgr.1\CLSID]
@ = "{BD15F01E-D575-42C9-8E88-C331391FDFA6}"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.odIPSecRoute]
@ = "odIPSecRoute Class"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.odIPSecRoute\CLSID]
@ = "{749EDDC6-1AED-418C-A49C-0B5E67AF8A27}"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.odIPSecRoute.1]
@ = "odIPSecRoute Class"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.odIPSecRoute.1\CLSID]
@ = "{749EDDC6-1AED-418C-A49C-0B5E67AF8A27}"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.OdJuniperSetup]
@ = "OdJuniperSetup Class"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.OdJuniperSetup\CLSID]
@ = "{B911D855-FC84-4192-B0AF-B53CBAB83F54}"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.OdJuniperSetup\CurVer]
@ = "Odjpaservice.OdJuniperSetup.1"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.OdJuniperSetup.1]
@ = "OdJuniperSetup Class"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.OdJuniperSetup.1\CLSID]
@ = "{B911D855-FC84-4192-B0AF-B53CBAB83F54}"
[HKEY_CLASSES_ROOT\Wow6432Node\odjpaservice.OdMiniUnZip]
@ = "OdMiniUnZip Class"
[HKEY_CLASSES_ROOT\Wow6432Node\odjpaservice.OdMiniUnZip\CLSID]

```

```

@ = "{DF7A8815-F320-48ED-A219-DAAFB3C1FBD1}"
[HKEY_CLASSES_ROOT\Wow6432Node\odjpaservice.OdMiniUnZip\CurVer]

@ = "odjpaservice.OdMiniUnZip.1"
[HKEY_CLASSES_ROOT\Wow6432Node\odjpaservice.OdMiniUnZip.1]

@ = "OdMiniUnZip Class"
[HKEY_CLASSES_ROOT\Wow6432Node\odjpaservice.OdMiniUnZip.1\CLSID]

@ = "{DF7A8815-F320-48ED-A219-DAAFB3C1FBD1}"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.OdMiniZip]

@ = "OdMiniZip Class"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.OdMiniZip\CLSID]

@ = "{0462122E-567A-48D1-B585-A851C120537D}"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.OdMiniZip\CurVer]

@ = "Odjpaservice.OdMiniZip.1"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.OdMiniZip.1]

@ = "OdMiniZip Class"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.OdMiniZip.1\CLSID]

@ = "{0462122E-567A-48D1-B585-A851C120537D}"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.odSSLSession]

@ = "odSSLSession Class"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.odSSLSession\CLSID]

@ = "{4E5CA46B-FB17-4EC4-A676-0DD15230863D}"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.odSSLSession.1]

@ = "odSSLSession Class"
[HKEY_CLASSES_ROOT\Wow6432Node\Odjpaservice.odSSLSession.1\CLSID]

@ = "{4E5CA46B-FB17-4EC4-A676-0DD15230863D}"
[HKEY_CLASSES_ROOT\Wow6432Node\OdSCard.OdysseyAvailableSCardsFactory]

@ = "OdysseyAvailableSCardsFactory Class"
[HKEY_CLASSES_ROOT\Wow6432Node\OdSCard.OdysseyAvailableSCardsFactory\
CLSID]

```

@ = "{03104BE6-BDDE-4FC3-B52B-869836FB408F}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdSCard.OdysseyAvailableSCardsFactory\CurVer]

@ = "OdSCard.OdysseyAvailableSCardsFactory.1"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdSCard.OdysseyAvailableSCardsFactory.1]

@ = "OdysseyAvailableSCardsFactory Class"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdSCard.OdysseyAvailableSCardsFactory.1\CLSID]

@ = "{03104BE6-BDDE-4FC3-B52B-869836FB408F}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdService.OdysseyEngine]

@ = "OdysseyEngine Class"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdService.OdysseyEngine\CLSID]

@ = "{C4BB5277-BC02-4DE6-846F-E18A50095DF6}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdService.OdysseyEngine\CurVer]

@ = "OdService.OdysseyEngine.1"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdService.OdysseyEngine.1]

@ = "OdysseyEngine Class"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdService.OdysseyEngine.1\CLSID]

@ = "{C4BB5277-BC02-4DE6-846F-E18A50095DF6}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdServiceDialogs.OdServiceDialogMgr]

@ = "OdServiceDialogMgr Class"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdServiceDialogs.OdServiceDialogMgr\CLSID]

@ = "{71486BF6-30BD-4D9B-AD24-3AF8854B7D1E}"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdServiceDialogs.OdServiceDialogMgr\CurVer]

@ = "OdServiceDialogs.OdServiceDialogMgr.1"

[HKEY\_CLASSES\_ROOT\Wow6432Node\OdServiceDialogs.OdServiceDialogMgr.1]

@ = "OdServiceDialogMgr Class"

























































