



Unified Access Control

Client Side Changes Guide

Release 3.1

Juniper Networks, Inc.
1194 North Mathilda Avenue
Sunnyvale, CA 94089
USA
408-745-2000
www.juniper.net

This product includes the Envoy SNMP Engine, developed by Epilogue Technology, an Integrated Systems Company. Copyright © 1986–1997, Epilogue Technology Corporation. All rights reserved. This program and its documentation were developed at private expense, and no part of them is in the public domain.

This product includes memory allocation software developed by Mark Moraes, copyright © 1988, 1989, 1993, University of Toronto.

This product includes FreeBSD software developed by the University of California, Berkeley, and its contributors. All of the documentation and software included in the 4.4BSD and 4.4BSD-Lite Releases is copyrighted by The Regents of the University of California. Copyright © 1979, 1980, 1983, 1986, 1988, 1989, 1991, 1992, 1993, 1994. The Regents of the University of California. All rights reserved.

GateD software copyright © 1995, The Regents of the University. All rights reserved. Gate Daemon was originated and developed through release 3.0 by Cornell University and its collaborators. Gated is based on Kirton's EGP, UC Berkeley's routing daemon (routed), and DCN's HELLO routing protocol. Development of Gated has been supported in part by the National Science Foundation. Portions of the GateD software copyright © 1988, Regents of the University of California. All rights reserved. Portions of the GateD software copyright © 1991, D. L. S. Associates.

Juniper Networks, the Juniper Networks logo, NetScreen, NetScreen Technologies, the NetScreen logo, NetScreen-Global Pro, ScreenOS, and GigaScreen are registered trademarks of Juniper Networks, Inc. in the United States and other countries.

The following are trademarks of Juniper Networks, Inc.: ERX, E-series, ESP, Instant Virtual Extranet, Internet Processor, J2300, J4300, J6300, J-Protect, J-series, J-Web, JUNOS, JUNOScope, JUNOScript, JUNOSe, M5, M7i, M10, M10i, M20, M40, M40e, M160, M320, M-series, MMD, NetScreen-5GT, NetScreen-5XP, NetScreen-5XT, NetScreen-25, NetScreen-50, NetScreen-204, NetScreen-208, NetScreen-500, NetScreen-5200, NetScreen-5400, NetScreen-IDP 10, NetScreen-IDP 100, NetScreen-IDP 500, NetScreen-Remote Security Client, NetScreen-Remote VPN Client, NetScreen-SA 1000 Series, NetScreen-SA 3000 Series, NetScreen-SA 5000 Series, NetScreen-SA Central Manager, NetScreen Secure Access, NetScreen-SM 3000, NetScreen-Security Manager, NMC-RX, SDX, Stateful Signature, T320, T640, T-series, and TX Matrix. All other trademarks, service marks, registered trademarks, or registered service marks are the property of their respective owners. All specifications are subject to change without notice.

Products made or sold by Juniper Networks or components thereof might be covered by one or more of the following patents that are owned by or licensed to Juniper Networks: U.S. Patent Nos. 5,473,599, 5,905,725, 5,909,440, 6,192,051, 6,333,650, 6,359,479, 6,406,312, 6,429,706, 6,459,579, 6,493,347, 6,538,518, 6,538,899, 6,552,918, 6,567,902, 6,578,186, and 6,590,785.

Copyright © 2006–2009, Juniper Networks, Inc.
All rights reserved. Printed in USA.

Juniper Networks assumes no responsibility for any inaccuracies in this document. Juniper Networks reserves the right to change, modify, transfer, or otherwise revise this publication without notice.

Software License

The terms and conditions for using this software are described in the software license contained in the acknowledgment to your purchase order or, to the extent applicable, to any reseller agreement or end-user purchase agreement executed between you and Juniper Networks. By using this software, you indicate that you understand and agree to be bound by those terms and conditions.

Generally speaking, the software license restricts the manner in which you are permitted to use the software and may contain prohibitions against certain uses. The software license may state conditions under which the license is automatically terminated. You should consult the license for further details.

For complete product documentation, please see the Juniper Networks Web site at www.juniper.net/techpubs.

End User License Agreement

READ THIS END USER LICENSE AGREEMENT ("AGREEMENT") BEFORE DOWNLOADING, INSTALLING, OR USING THE SOFTWARE. BY DOWNLOADING, INSTALLING, OR USING THE SOFTWARE OR OTHERWISE EXPRESSING YOUR AGREEMENT TO THE TERMS CONTAINED HEREIN, YOU (AS CUSTOMER OR IF YOU ARE NOT THE CUSTOMER, AS A REPRESENTATIVE/AGENT AUTHORIZED TO BIND THE CUSTOMER) CONSENT TO BE BOUND BY THIS AGREEMENT. IF YOU DO NOT OR CANNOT AGREE TO THE TERMS CONTAINED HEREIN, THEN (A) DO NOT DOWNLOAD, INSTALL, OR USE THE SOFTWARE, AND (B) YOU MAY CONTACT JUNIPER NETWORKS REGARDING LICENSE TERMS.

1. The Parties. The parties to this Agreement are Juniper Networks, Inc. and its subsidiaries (collectively "Juniper"), and the person or organization that originally purchased from Juniper or an authorized Juniper reseller the applicable license(s) for use of the Software ("Customer") (collectively, the "Parties").

2. The Software. In this Agreement, "Software" means the program modules and features of the Juniper or Juniper-supplied software, and updates and releases of such software, for which Customer has paid the applicable license or support fees to Juniper or an authorized Juniper reseller.

3. License Grant. Subject to payment of the applicable fees and the limitations and restrictions set forth herein, Juniper grants to Customer a non-exclusive and non-transferable license, without right to sublicense, to use the Software, in executable form only, subject to the following use restrictions:

- Customer shall use the Software solely as embedded in, and for execution on, Juniper equipment originally purchased by Customer from Juniper or an authorized Juniper reseller, unless the applicable Juniper documentation expressly permits installation on non-Juniper equipment.
- Customer shall use the Software on a single hardware chassis having a single processing unit, or as many chassis or processing units for which Customer has paid the applicable license fees.
- Product purchase documents, paper or electronic user documentation, and/or the particular licenses purchased by Customer may specify limits to Customer's use of the Software. Such limits may restrict use to a maximum number of seats, registered endpoints, concurrent users, sessions, calls, connections, subscribers, clusters, nodes, or transactions, or require the purchase of separate licenses to use particular features, functionalities, services, applications, operations, or capabilities, or provide throughput, performance, configuration, bandwidth, interface, processing, temporal, or geographical limits. Customer's use of the Software shall be subject to all such limitations and purchase of all applicable licenses.

The foregoing license is not transferable or assignable by Customer. No license is granted herein to any user who did not originally purchase the applicable license(s) for the Software from Juniper or an authorized Juniper reseller.

4. Use Prohibitions. Notwithstanding the foregoing, the license provided herein does not permit the Customer to, and Customer agrees not to and shall not: (a) modify, unbundle, reverse engineer, or create derivative works based on the Software; (b) make unauthorized copies of the Software (except as necessary for backup purposes); (c) rent, sell, transfer, or grant any rights in and to any copy of the Software, in any form, to any third party; (d) remove any proprietary notices, labels, or marks on or in any copy of the Software or any product in which the Software is embedded; (e) distribute any copy of the Software to any third party, including as may be embedded in Juniper equipment sold in the secondhand market; (f) use any "locked" or key-restricted feature, function, service, application, operation, or capability without first purchasing the applicable license(s) and obtaining a valid key from Juniper, even

if such feature, function, service, application, operation, or capability is enabled without a key; (g) distribute any key for the Software provided by Juniper to any third party; (h) use the Software in any manner that extends or is broader than the uses purchased by Customer from Juniper or an authorized Juniper reseller; (i) use the Software on non-Juniper equipment where the Juniper documentation does not expressly permit installation on non-Juniper equipment; (j) use the Software (or make it available for use) on Juniper equipment that the Customer did not originally purchase from Juniper or an authorized Juniper reseller; or (k) use the Software in any manner other than as expressly provided herein.

5. Audit. Customer shall maintain accurate records as necessary to verify compliance with this Agreement. Upon request by Juniper, Customer shall furnish such records to Juniper and certify its compliance with this Agreement.

6. Confidentiality. The Parties agree that aspects of the Software and associated documentation are the confidential property of Juniper. As such, Customer shall exercise all reasonable commercial efforts to maintain the Software and associated documentation in confidence, which at a minimum includes restricting access to the Software to Customer employees and contractors having a need to use the Software for Customer's internal business purposes.

7. Ownership. Juniper and Juniper's licensors, respectively, retain ownership of all right, title, and interest (including copyright) in and to the Software, associated documentation, and all copies of the Software. Nothing in this Agreement constitutes a transfer or conveyance of any right, title, or interest in the Software or associated documentation, or a sale of the Software, associated documentation, or copies of the Software.

8. Warranty, Limitation of Liability, Disclaimer of Warranty. The warranty applicable to the Software shall be as set forth in the warranty statement that accompanies the Software (the "Warranty Statement"). Nothing in this Agreement shall give rise to any obligation to support the Software. Support services may be purchased separately. Any such support shall be governed by a separate, written support services agreement. TO THE MAXIMUM EXTENT PERMITTED BY LAW, JUNIPER SHALL NOT BE LIABLE FOR ANY LOST PROFITS, LOSS OF DATA, OR COSTS OR PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES, OR FOR ANY SPECIAL, INDIRECT, OR CONSEQUENTIAL DAMAGES ARISING OUT OF THIS AGREEMENT, THE SOFTWARE, OR ANY JUNIPER OR JUNIPER-SUPPLIED SOFTWARE. IN NO EVENT SHALL JUNIPER BE LIABLE FOR DAMAGES ARISING FROM UNAUTHORIZED OR IMPROPER USE OF ANY JUNIPER OR JUNIPER-SUPPLIED SOFTWARE. EXCEPT AS EXPRESSLY PROVIDED IN THE WARRANTY STATEMENT TO THE EXTENT PERMITTED BY LAW, JUNIPER DISCLAIMS ANY AND ALL WARRANTIES IN AND TO THE SOFTWARE (WHETHER EXPRESS, IMPLIED, STATUTORY, OR OTHERWISE), INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NONINFRINGEMENT. IN NO EVENT DOES JUNIPER WARRANT THAT THE SOFTWARE, OR ANY EQUIPMENT OR NETWORK RUNNING THE SOFTWARE, WILL OPERATE WITHOUT ERROR OR INTERRUPTION, OR WILL BE FREE OF VULNERABILITY TO INTRUSION OR ATTACK. In no event shall Juniper's or its suppliers' or licensors' liability to Customer, whether in contract, tort (including negligence), breach of warranty, or otherwise, exceed the price paid by Customer for the Software that gave rise to the claim, or if the Software is embedded in another Juniper product, the price paid by Customer for such other product. Customer acknowledges and agrees that Juniper has set its prices and entered into this Agreement in reliance upon the disclaimers of warranty and the limitations of liability set forth herein, that the same reflect an allocation of risk between the Parties (including the risk that a contract remedy may fail of its essential purpose and cause consequential loss), and that the same form an essential basis of the bargain between the Parties.

9. Termination. Any breach of this Agreement or failure by Customer to pay any applicable fees due shall result in automatic termination of the license granted herein. Upon such termination, Customer shall destroy or return to Juniper all copies of the Software and related documentation in Customer's possession or control.

10. Taxes. All license fees for the Software are exclusive of taxes, withholdings, duties, or levies (collectively "Taxes"). Customer shall be responsible for paying Taxes arising from the purchase of the license, or importation or use of the Software.

11. Export. Customer agrees to comply with all applicable export laws and restrictions and regulations of any United States and any applicable foreign agency or authority, and not to export or re-export the Software or any direct product thereof in violation of any such restrictions, laws or regulations, or without all necessary approvals. Customer shall be liable for any such violations. The version of the Software supplied to Customer may contain encryption or other capabilities restricting Customer's ability to export the Software without an export license.

12. Commercial Computer Software. The Software is "commercial computer software" and is provided with restricted rights. Use, duplication, or disclosure by the United States government is subject to restrictions set forth in this Agreement and as provided in DFARS 227.7201 through 227.7202-4, FAR 12.212, FAR 27.405(b)(2), FAR 52.227-19, or FAR 52.227-14(ALT III) as applicable.

13. Interface Information. To the extent required by applicable law, and at Customer's written request, Juniper shall provide Customer with the interface information needed to achieve interoperability between the Software and another independently created program, on payment of applicable fee, if any. Customer shall observe strict obligations of confidentiality with respect to such information and shall use such information in compliance with any applicable terms and conditions upon which Juniper makes such information available.

14. Third Party Software. Any licensor of Juniper whose software is embedded in the Software and any supplier of Juniper whose products or technology are embedded in (or services are accessed by) the Software shall be a third party beneficiary with respect to this Agreement, and such licensor or vendor shall have the right to enforce this Agreement in its own name as if it were Juniper. In addition, certain third party software may be provided with the Software and is subject to the accompanying license(s), if any, of its respective owner(s). To the extent portions of the Software are distributed under and subject to open source licenses obligating Juniper to make the source code for such portions publicly available (such as the GNU General Public License ("GPL") or the GNU Library General Public License ("LGPL")), Juniper will make such source code portions (including Juniper modifications, as appropriate) available upon request for a period of up to three years from the date of distribution. Such request can be made in writing to Juniper Networks, Inc., 1194 N. Mathilda Ave., Sunnyvale, CA 94089, ATTN: General Counsel. You may obtain a copy of the GPL at <http://www.gnu.org/licenses/gpl.html>, and a copy of the LGPL at <http://www.gnu.org/licenses/lgpl.html>.

15. Miscellaneous. This Agreement shall be governed by the laws of the State of California without reference to its conflicts of laws principles. The provisions of the U.N. Convention for the International Sale of Goods shall not apply to this Agreement. For any disputes arising under this Agreement, the Parties hereby consent to the personal and exclusive jurisdiction of, and venue in, the state and federal courts within Santa Clara County, California. This Agreement constitutes the entire and sole agreement between Juniper and the Customer with respect to the Software, and supersedes all prior and contemporaneous agreements relating to the Software, whether oral or written (including any inconsistent terms contained in a purchase order), except that the terms of a separate written agreement executed by an authorized Juniper representative and Customer shall govern to the extent such terms are inconsistent or conflict with terms contained herein. No modification to this Agreement nor any waiver of any rights hereunder shall be effective unless expressly assented to in writing by the party to be charged. If any portion of this Agreement is held invalid, the Parties agree that such invalidity shall not affect the validity of the remainder of this Agreement. This Agreement and associated documentation has been written in the English language, and the Parties agree that the English version will govern. (For Canada: Les parties aux présentés confirment leur volonté que cette convention de même que tous les documents y compris tout avis qui s'y rattache, soient rédigés en langue anglaise. (Translation: The parties confirm that this Agreement and all related documentation is and will be in the English language).)

Client-Side Application Changes Guide

This guide lists the names of the package files used by the IVE to install client-side components, the names of the files the packages install and uninstall, and the registry changes the files make to the user's system. It also describes the permissions that are required to install and run various IVE client-side components.

- “Juniper Unified Network Services” on page 1
- “Odyssey Access Client on Windows XP and Windows Vista 32-bit” on page 3
- “Odyssey Access Client on Windows Vista 64-bit” on page 33
- “Odyssey Access Client on Macintosh” on page 101
- “Host Checker” on page 102

Juniper Unified Network Services

The UAC Agent installer includes the Juniper Unified Network Service. The Juniper Unified Network Services provides a wide array of core network and security services including encryption, Layer 3 enforcement, and an infrastructure to download, install, upgrade, and execute Juniper-signed client-side applications without Administrator privileges.

Package file and file location

C:\Windows\Downloaded Program Files\JuniperSetup.ocx

Additional files installed by package and file locations

The Juniper Unified Network Service installs the following additional files in the C:\Program Files\Common Files\Juniper Networks\JUNS directory:

- access.ini
- versionInfo.ini
- dbghelp.dll
- dsAccessService.exe
- dsInstallerService.dll
- dsLogService.dll

- Uninstall.exe
- install.log
- JuniperSetupClientOCX.exe
- JuniperSetupOCX.exe
- uninstall.exe.manifest

Files remaining after uninstall

- install.log
- JuniperSetupClientOCX

Registry modifications

The Juniper Unified Network Service sets the following value in HKLM\Software\Juniper Networks\Common Files\dsLogService

- String dsLogService. Set to %Program Files%\Common Files\Juniper Networks\JUNS\dsLogService.dll.

The Juniper Unified Network Service sets the following values in HKLM\Software\Juniper Networks\Logging\Level

- String Level. Set to “3”
- String LogFileName. Set to “%DocumentsAndSettings%\All Users\Application Data\Juniper Networks\Logging\debuglog.log”
- String LogSize. Set to “10”

The Juniper Unified Network Service sets the following values in HKLM\System\CurrentControlSet\Service\JuniperAccessService\Description

- String Description. Set to “Manages Juniper Networks Software”
- String DisplayName. Set to “Juniper Unified Network Service”
- Dword Error Control. Set to “0x00000000”
- String Failure Actions. Set to “Binary Data”
- String ImagePath. Set to “%Program Files%\Common Files\Juniper Networks\JUNS\dsAccessService.exe”
- String ObjectName. Set to “LocalSystem”
- Dword Start. Set to “0x00000002”
- Dword Type. Set to “0x00000110”

The Juniper Unified Network Service sets the following values in HKLM\System\CurrentControlSet\Service\JuniperAccessService\Description

- String 0. Set to “Root\LEGACY_JUNIPERACCESSSERVICE\0000”
- Dword Count. Set to “0x00000001”
- Dword NextInstance. Set to “0x00000001”
- String Security. Set to “Binary Data”

Tunnel Manager

Files installed and file locations

Tunnel Manager installs the following additional files in the C:\Program Files\Common Files\Juniper Networks\Tunnel Manager directory:

- dstmclient.dll
- dstmservice.dll
- dstunnelmanager.dll
- tm.dep
- uninstall.exe
- versioninfo.ini
- install.log
- uninstall.exe.manifest

Files remaining after uninstall

- install.log

Registry modifications

Tunnel manager sets the following values in HKEY_LOCAL_MACHINE\SOFTWARE\Juniper Networks\Common Files:

- String dsTMClient. Set to C:\Program Files\Common Files\Juniper Networks\Tunnel Manager\dsTMClient.dll
- String dsTunnelManager. Set to C:\Program Files\Common Files\Juniper Networks\Tunnel Manager\dsTunnelManager.dll

Odyssey Access Client on Windows XP and Windows Vista 32-bit

To run the Odyssey Access Client, the IVE downloads the OdysseyAccessClient.msi package to the user's client. This package is responsible for downloading additional files to the user's system in order to run the Odyssey Access Client.

Package file and file location

The OdysseyAccessClient.msi package is installed in C:\Documents and Settings\All Users\Application Data\Juniper Networks\UAC Agent\.

The Odyssey Access Client application is installed in C:\Program Files\Juniper Networks\Odyssey Access Client\odClientService.exe.

Files remaining after uninstall

- C:\WINDOWS\system32\drivers\jnprvamgr.sys
- C:\WINDOWS\system32\drivers\jnprva.sys

Additional files installed by package and file locations

The Odyssey Access Client installs the following files on the client in the C:\Program Files\Common Files\Funk Software directory:

- dcfDOM.dll
- dcfLibrary.dll
- odCert_M.dll
- odConsole.dll
- odFips.dll
- odFips.dll.icv
- odLib_OSSL.dll
- odShadow.dll

On Windows XP The Odyssey Access Client installs the following files on the client in the C:\Program Files\Common Files\Juniper Networks\JNPRNA directory:

- jnprna.cat
- jnprna.dll
- jnprna.inf
- jnprna.sys
- jnprna_m.cat
- jnprna_M.inf
- jnprnaapi.dll
- jnprnaNetInstall.dll
- jnprva.inf
- jnprvamgr.dll
- nsStatsDump.exe

- uninst.exe
- versionInfo.ini
- install.log

In Windows Vista (32-bit), the Odyssey Access Client installs the following files on the client in the C:\Program Files\Common Files\Juniper Networks\JNPRNA directory:

- DriverUI.exe
- jnprna.cat
- jnprna.inf
- jnprna.sys
- jnprna_m.cat
- jnprna_m.inf
- jnprnaapi.dll
- jnprnaNetInstall.dll
- jnprnaNetInstallTest.exe
- jnprva.cat
- jnprva.inf
- jnprva.sys
- jnprvamgr.cat
- jnprvamgr.dll
- jnprvamgr.inf
- jvaTest.exe
- nsStatsDump.exe
- uninst.exe
- x64/jnprNetInstall.dll
- install.log
- versionInfo.ini

Files remaining after uninstall

- install.log
- jnprnaNetInstall.log

The Odyssey Access Client installs the following files on the client in the C:\Program Files\Common Files\Juniper Networks\JSCDT directory:

- jnprShare.dll

Additionally, in Windows Vista the following file is installed.

- jnprShare.txt
- jnprShare.lock
- jnprShare.log

The Odyssey Access Client installs the following files on the client in the C:\Program Files\Common Files\Juniper Networks\JUNS directory:

- access.ini
- DbgHelp.dll
- dsAccessService.exe
- dsInstallerService.dll
- dsLogService.dll
- JuniperSetupClientOCX.exe
- JuniperSetupOCX.exe
- Uninstall.exe
- Uninstall.exe.manifest
- versionInfo.ini

On Windows XP the Odyssey Access Client installs the following files on the client in the C:\Program Files\Common Files\Juniper Networks\TNC Client directory:

- AVManager.dll
- CAntiVirusCOM.dll
- CertAuthIMC.dll
- CFireWallCOM.dll
- dsHostCheckerResource_DE.dll
- dsHostCheckerResource_EN.dll
- dsHostCheckerResource_ES.dll
- dsHostCheckerResource_FR.dll
- dsHostCheckerResource_JA.dll

- dsHostCheckerResource_KO.dll
- dsHostCheckerResource_ZH.dll
- dsHostCheckerResource_ZH_CN.dll
- dsnsisdll.dll
- efc.dll
- dsWinClient.dll
- EPCheck.dll
- hcimc.dll
- install.log
- jsystemimc.dll
- jTnccNarProxy.dll
- jTnccService.exe
- msvcp60.dll
- patchlinkimc.dll
- ShavlikIMC.dll
- uninstall.exe
- UnifiedSDK.ini
- versionInfo.ini

In Windows Vista (32-bit), the Odyssey Access Client installs the following files on the client in the C:\Program Files\Common Files\Juniper Networks\TNC Client directory:

- AVManager.dll
- CAntiVirusCOM.dll
- CertAuthIMC.dll
- CFireWallCOM.dll
- dsHostCheckerResource_DE.dll
- dsHostCheckerResource_EN.dll
- dsHostCheckerResource_ES.dll
- dsHostCheckerResource_FR.dll
- dsHostCheckerResource_JA.dll

- dsHostCheckerResource_KO.dll
- dsHostCheckerResource_ZH.dll
- dsHostCheckerResource_ZH_CN.dll
- dsnsisdll.dll
- efc.dll
- dsWinClient.dll
- EPCheck.dll
- FWManager.dll
- hcimc.dll
- install.log
- jsystemimc.dll
- jTnccNarProxy.dll
- jTnccService.exe
- msvcp60.dll
- OPSWATAVCommon.dll
- OPSWATProcessesScanner.dll
- patchlinkimc.dll
- pinfo.dat
- ShavlikIMC.dll
- TNCC.dep
- uninstall.exe
- UnifiedSDK.ini
- versionInfo.inni
- hfnetchk6b.xml
- HFVersions cab file
- Manifest XML
- stPatchAssesment.dll
- stUpdateManager.dll

In Windows Vista (32-bit), the Odyssey Access Client installs the following files on the client in the C:\Program Files\Common Files\Juniper Networks\TNC Client\AV directory:

- AEC_AV.dll
- AhnLabAS.dll
- AhnLabAV.dll
- ALWIL.dll
- AnonymizerAS.dll
- AOL.dll
- AolAV.dll
- Authentium.dll
- AuthentiumAS.dll
- BitDefenderAS.dll
- BitDefenderAV.dll
- Bullet_Proof_Soft.dll
- Check_PointAS.dll
- Check_PointAV.dll
- ClamAV.dll
- ClamWin.dll
- Computer_Associates_International.dll
- DefenderProAV.dll
- EarthLinkAS.dll
- EarthLinkAV.dll
- Eset.dll
- FaceTimeAS.dll
- Frisk_Software_International.dll
- F-SecureAV.dll
- GData.dll
- Gridsoft.dll

- HauriAV.dll
- HBEDV.dll
- ISSAV.dll
- Javacool_Software.dll
- Jiangmin.dll
- Kaspersky_Labs.dll
- KingSoft.dll
- Lavasoft.dll
- McAfeeAS.dll
- McAfeeAV.dll
- MicroSmarts.dll
- Microsoft_Corporation.dll
- MicrosoftAV.dll
- MicroWorld.dll
- NormanAV.dll
- NortonAS.dll
- NortonAV.dll
- Panda_Software.dll
- PC_Tools.dll
- PestPatrol.dll
- Prevx_Ltd.dll
- RadialPointAS.dll
- RadialPointAV.dll
- RisingAV.dll
- SalD.dll
- SBC_Yahoo_AntiVirus_Component.dll
- SerenitiAS.dll
- SerenitiAV.dll

- SophosAV.dll
- SpyBot.dll
- SunbeltAS.dll
- TrendMicroAS.dll
- TrendMicroAV.dll
- VCOMAS.dll
- VCOMAV.dll
- Webroot.dll
- Yahoo.dll
- Zone_Labs.dll

The Odyssey Access Client installs the following files on the client in the C:\Program Files\Common Files\Juniper Networks\Tunnel Manager directory:

- dsTMClient.dll
- dsTMService.dll
- dsTunnelManager.dll
- TM.dep
- Uninstall.exe
- Uninstall.exe.manifest
- versionInfo.ini

On Windows XP the Odyssey Access Client installs the following files on the client in the C:\Program Files\Juniper Networks\Odyssey Access Client directory:

- AccessServiceSetup.exe
- AccessServiceComponent.exe
- ClientPreset.xml
- dsNetworkMonitor.dll
- epdiag.dll
- jnprnaInstall.exe
- odClient.chm
- odClientAdministrator.exe
- odClientControl.dll

- odClientFE.chm
- odClientMgr.exe
- odClientMgrDialogs.dll
- odClientResource0009.dll
- odClientService.exe
- Odcpl.cpl
- odGinaLibrary.dll
- odjpaservice.dll
- odLogin.dll
- odLoginScript.exe
- odPush.dat
- odSCard.dll
- odService.dll
- odServiceDialogs.dll
- odServiceResource0009.dll
- odSupExt.dll
- OdTray.exe
- odyEvent.dll
- odyGina.dll
- odyNwLgXctl.ocx
- readme.txt
- TnccSetup.exe
- Wrapper.exe

On Windows Vista (32-bit) the Odyssey Access Client installs the following files on the client in the C:\Program Files\Juniper Networks\Odyssey Access Client directory:

- AccessServiceSetup.exe
- AccessServiceComponent.exe
- ClientPreset.xml
- dsNetworkMonitor.dll
- epdiag.dll
- jnprnaInstall.exe

- JNPRCredProv.dll
- JNPRIhvExt.dll
- JNPRSmartCardProv.dll
- odClient.chm
- odClientAdministrator.exe
- odClientControl.dll
- odClientFE.chm
- odClientMgr.exe
- odClientMgrDialogs.dll
- odClientResource0009.dll
- odClientService.exe
- Odcpl.cpl
- odGinaLibrary.dll
- odjpaservice.dll
- odLogin.dll
- odLoginScript.exe
- odPush.dat
- odSCard.dll
- odService.dll
- odServiceDialogs.dll
- odServiceResource0009.dll
- odSuppExt.dll
- OdTray.exe
- odyNwLgXctl.ocx
- readme.txt
- TnccSetup.exe
- TunnelManagerSetup.exe
- Wrapper.exe

In Windows Vista (32-bit), the Odyssey Access Client installs the following files on the client in the C:\Program Files\Common Files\Juniper Networks\Odyssey Access Client directory:

- AccessServiceComponent.exe
- ClientPreset.xml
- dsNetworkMonitor.dll
- epdiag.dll
- JNPRCredProv.dll
- JNPRHvExt.dll
- jnprnaInstall.exe
- JNPRSmartCardProv.dll
- odClient.chm
- odClientAdministrator.exe
- odClientControl.dll
- odClientMgr.exe
- odClientMgrDialogs.dll
- odClientResource0009.dll
- odClientService.exe
- Odcp1.cpl
- odGinaLibrary.dll
- odGinaLibrary64.dll
- odjpaservice.dll
- odLogin.dll
- odLoginScript.exe
- odPush.dat
- odSCard.dll
- odService.dll
- odServiceDialogs.dll
- odServiceResource0009.dll
- OdTray.exe
- odyEvent.dll

- odyGina.dll
- odyNwLgXctl.ocx
- readme.txt
- TnccSetup.exe
- TunnelManagerComponent.exe

Files remaining after uninstall

- odInitialSettings.xml

In Windows Vista (32-bit), the Odyssey Access Client installs the following files on the client in the C:\Users\\AppData\Roaming\Juniper Networks\UAC Agent directory, and in the C:\Documents and Settings\\Application Data\Juniper Networks\UAC Agent directory:

- dsInstallerClient.dll
- dsLogService.dll
- install.log
- OACInstall.log
- remove1x.exe

In Windows XP the Odyssey Access Client installs the following file on the client in the C:\Documents and Settings\All Users\Application Data directory:

- NeoterisSetup.OCX

Files remaining after uninstall

- NeoterisSetup.OCX

On Windows XP the Odyssey Access Client installs the following directory on the client:

- C:\Users\\AppData\Roaming\Juniper Networks\Infranet Agent

On Windows Vista (32-bit) the Odyssey Access Client installs the following directory on the client:

- C:\Documents and Settings\\Application Data\Juniper Networks\Infranet Agent

On Windows XP the Odyssey Access Client installs the following files on the client in the C:\Documents and Settings\\Application Data\Juniper Networks\Setup Client directory:

- JuniperSetupCtrl.log
- JuniperSetupApp.log

- JuniperSetupApp.exe
- JuniperSetupDLL.log
- odInitialScript.xml
- string_de.properties
- string_en.properties
- string_es.properties
- string_fr.properties
- string_ja.properties
- string_ko.properties
- string_zh.properties
- string_zh_cn.properties
- versionInfo.ini
- NeoterisSetup.ocx
- JuniperSetupCtrl.log
- JuniperSetupClient.ini
- JuniperSetupDLL.log
- JuniperSetupClientOCX.exe
- JuniperSetupDLL.dll
- dsLogService.dll

In Windows Vista (32-bit), the Odyssey Access Client installs the following files on the client in the C:\Users\\AppData\Roaming\Juniper Networks\Setup Client directory:

- dsLogService.dll
- JuniperSetupClient.exe
- JuniperSetupClient.log
- JuniperSetupClient.ini
- JuniperSetupClientOCX.exe
- JuniperSetupDLL.dll
- uninstallOCX.exe

- Client\newScripts

The Odyssey Access Client installs the following directory on the client:

- C:\Documents and Settings\\Application Data\Funk software\Odyssey
- C:\Users\\AppData\Roaming\Funk Software\Odyssey\newScripts
- C:\Documents and Settings\All Users\Application Data\Juniper Networks\Logging

The Odyssey Access Client installs the following files on the client in the C:\WINDOWS\System32\drivers directory:

- jnprna.sys
- jnprvamgr.sys
- odFIPS.sys
- odFIPS.sys.icv
- The Virtual Adapter driver, jnprva.sys (installed On-Demand)

Files remaining after uninstall

- Jnprvamgr.sys
- Jnprva.sys (will remain only if installed)

The Odyssey Access Client installs the following files on the client in the C:\Documents and Settings\\Application Data\Juniper Networks directory:

- SetupVersionInfo.ini

On Windows XP the Odyssey Access Client installs the following files on the client in the C:\Documents and Settings\All Users\Application Data\Juniper Networks\UAC Agent directory:

- oac.tmp

In Windows Vista (32-bit), the Odyssey Access Client installs the following hidden file on the client in the C:\ProgramData\Juniper Networks\UAC Agent directory:

- OACUninstall.log

Files remaining after uninstall

- OACUninstall.log

The Odyssey Access Client installs the following files on the client in the C:\Program Files\Juniper Networks\UAC Agent directory:

- UACAgent.dep

- versionInfo.ini

The Odyssey Access Client installs the following files on the client in the C:\Windows\System32\drivers directory:

- jnprna.sys
- odFIPS.sys
- odFIPS.sys.icv

The Odyssey Access Client installs the following files on the client in the C:\Windows\System32\drivers directory:

- odFIPS.sys
- odFIPS.sys.icv

The Odyssey Access Client installs the following files on the client in the C:\Windows\System32 directory:

- msvcm80.dll
- msvcp60.dll
- msvcp80.dll
- msvcr80.dll
- msvcrt.dll
- Odcp1.cpl
- odSendPacket.dll

The Odyssey Access Client installs the following file on the client in the C:\Windows\Documents and Settings\\Application Data\Juniper Networks\Setup directory:

- odInitialScript.xml

In Windows Vista (32-bit), the Odyssey Access Client installs the following files on the client in the C:\Windows\winxs\Manifests directory:

- x86_Microsoft.VC80.CRT_1fc8b3b9a1e18e3b_8.0.50727.762_x-ww_6b128700.cat
- x86_Microsoft.VC80.CRT_1fc8b3b9a1e18e3b_8.0.50727.762_x-ww_6b128700.manifest

In Windows Vista (32-bit), the Odyssey Access Client installs the following files on the client in the C:\Windows\winxs\Policies\x86_policy.80.Microsoft.VC80.CRT_1fc8b3b9a1e18e3b_x-ww_77c24773 directory:

- 8.0.50727.762.cat

- 7.0.50727.762.policy

In Windows Vista (32-bit), the Odyssey Access Client installs the following files on the client in the

C:\Windows\winxs\x86_microsoft.vc80.crt_1fc8b3b9a1e18e3b_8.0.50727.762_none_10b2f55f9bffb8f8 directory:

- msvcm80.dll
- msvcp80.dll
- msvcr80.dll
- x86_Microsoft.VC80.CRT_1fc8b3b9a1e18e3b_8.0.50727.762_x-ww_6b128700.cat
- x86_Microsoft.VC80.CRT_1fc8b3b9a1e18e3b_8.0.50727.762_x-ww_6b128700.manifest

In Windows Vista (32-bit), the Odyssey Access Client installs the following files on the client in the

C:\Windows\winxs\x86_Microsoft\VC80.CRT_1fc8b3b9a1e18e3b_8.0.50727.762_x-ww_6b128700 directory:

- msvcm80.dll
- msvcp80.dll
- msvcr80.dll

In Windows Vista (32-bit), the Odyssey Access Client installs the following files on the client in the

C:\Windows\winxs\x86_policy.8.0.microsoft.vc80.crt_1fc8b3b9a1e18e3b_8.0.50727.762_none_9193a620671dde41 directory:

- 8.0.50727.762.cat
- 8.0.50727.762.policy

Registry modifications

The Odyssey Access Client sets the following registry files:

- String Default is set to “ConfigUI Class” in HKEY_CLASSES_ROOT\odClientMgrDialogs.ConfigUI
- String Default is set to “{473D6B6A-AA07-4098-8546-1A15D020F9EE}” in HKEY_CLASSES_ROOT\odClientMgrDialogs.ConfigUI\CLSID
- String Default is set to “odClientMgrDialogs.ConfigUI.1” in HKEY_CLASSES_ROOT\odClientMgrDialogs.ConfigUI\CurVer
- String Default is set to “ConfigUI Class” in HKEY_CLASSES_ROOT\odClientMgrDialogs.ConfigUI.1

- String Default is set to "{473D6B6A-AA07-4098-8546-1A15D020F9EE}" in HKEY_CLASSES_ROOT\odClientMgrDialogs.ConfigUI.1\CLSID
- String Default is set to "OdConsoleDialog Class" in HKEY_CLASSES_ROOT\CLSID\{6B891951-71B6-405E-B9E8-3250FCF4BC51}
- String Default is set to "CommonFilesFolder\Funk Software\odConsole.dll" and string ThreadingModel is set to "Free" in HKEY_CLASSES_ROOT\CLSID\{6B891951-71B6-405E-B9E8-3250FCF4BC51}\InprocServer32
- String Default is set to "OdConsole.OdConsoleDialog.1" in HKEY_CLASSES_ROOT\CLSID\{6B891951-71B6-405E-B9E8-3250FCF4BC51}\ProgID
- String Default is set to "{17689671-9839-463D-9DAC-2800AA4D74F5}" in HKEY_CLASSES_ROOT\CLSID\{6B891951-71B6-405E-B9E8-3250FCF4BC51}\TypeLib
- String Default is set to "OdClientControl.OdClientConfigurationDatabase" in HKEY_CLASSES_ROOT\CLSID\{6B891951-71B6-405E-B9E8-3250FCF4BC51}\VersionIndependentProgID
- String Default is set to "OdConsoleLogStream Class" in HKEY_CLASSES_ROOT\CLSID\{CBBFB98A-CC29-440E-A62F-ADD5C69D25DC}
- String Default is set to "[CommonFilesFolder\Funk Software\odConsole.dll" and String ThreadingModel is set to "Free" in HKEY_CLASSES_ROOT\CLSID\{CBBFB98A-CC29-440E-A62F-ADD5C69D25DC}\InprocServer32
- String Default is set to "OdConsole.OdConsoleLogStream.1" in HKEY_CLASSES_ROOT\CLSID\{CBBFB98A-CC29-440E-A62F-ADD5C69D25DC}\ProgID
- String Default is set to "{6D396288-D452-4869-9895-4EEE4D3C8CF4}" in HKEY_CLASSES_ROOT\CLSID\{CBBFB98A-CC29-440E-A62F-ADD5C69D25DC}\TypeLib
- String Default is set to "OdConsole.OdConsoleLogStream" in HKEY_CLASSES_ROOT\CLSID\{CBBFB98A-CC29-440E-A62F-ADD5C69D25DC}\VersionIndependentProgID
- String ThreadingModel is set to "Free" in HKEY_CLASSES_ROOT\CLSID\{03104BE6-BDDE-4FC3-B52B-869836FB408F}\InprocServer32
- String Default is set to "{3880EABE-2031-47EA-8BB7-8E9709A41D7A}" in HKEY_CLASSES_ROOT\CLSID\{03104BE6-BDDE-4FC3-B52B-869836FB408F}\TypeLib
- String Default is set to "OdClientEngine Class" in HKEY_CLASSES_ROOT\CLSID\{0A3937EA-5A82-4363-A0CD-4245773C282C}

- String Default is set to “[INSTALLDIR]odClientControl.dll” and String ThreadingModel is set to “Both” in HKEY_CLASSES_ROOT\CLSID\{0A3937EA-5A82-4363-A0CD-4245773C282C}\InprocServer32
- String Default is set to “OdClientControl.OdClientEngine.1” in HKEY_CLASSES_ROOT\CLSID\{0A3937EA-5A82-4363-A0CD-4245773C282C}\ProgID
- Creates the key HKEY_CLASSES_ROOT\CLSID\{0A3937EA-5A82-4363-A0CD-4245773C282C}\Programmable
- String Default is set to “{17689671-9839-463D-9DAC-2800AA4D74F5}” in HKEY_CLASSES_ROOT\CLSID\{0A3937EA-5A82-4363-A0CD-4245773C282C}\TypeLib
- String Default is set to “OdClientControl.OdClientEngine” in HKEY_CLASSES_ROOT\CLSID\{0A3937EA-5A82-4363-A0CD-4245773C282C}\VersionIndependentProgID
- String Default is set to “OdClientConfigurationDatabase Class” in HKEY_CLASSES_ROOT\CLSID\{CF890798-FED6-49D3-A1F5-947BD485CC03}
- String Default is set to “[INSTALLDIR]odClientControl.dll” and String ThreadingModel is set to “Both” in HKEY_CLASSES_ROOT\CLSID\{CF890798-FED6-49D3-A1F5-947BD485CC03}\InprocServer32
- String Default is set to “OdClientControl.OdClientConfigurationDatabase.1” in HKEY_CLASSES_ROOT\CLSID\{CF890798-FED6-49D3-A1F5-947BD485CC03}\ProgID
- Creates the key HKEY_CLASSES_ROOT\CLSID\{CF890798-FED6-49D3-A1F5-947BD485CC03}\Programmable
- String Default is set to “{17689671-9839-463D-9DAC-2800AA4D74F5}” in HKEY_CLASSES_ROOT\CLSID\{CF890798-FED6-49D3-A1F5-947BD485CC03}\TypeLib
- String Default is set to “OdClientControl.OdClientConfigurationDatabase” in HKEY_CLASSES_ROOT\CLSID\{CF890798-FED6-49D3-A1F5-947BD485CC03}\VersionIndependentProgID
- String Default is set to “OdClientSecurityDatabase Class” in HKEY_CLASSES_ROOT\CLSID\{F24A7852-937D-4D9D-9086-8B976FE979E8}
- String Default is set to “[INSTALLDIR]odClientControl.dll” and String ThreadingModel is set to “Both” in HKEY_CLASSES_ROOT\CLSID\{F24A7852-937D-4D9D-9086-8B976FE979E8}\InprocServer32
- String Default is set to “OdClientControl.OdClientSecurityDatabase.1” in HKEY_CLASSES_ROOT\CLSID\{F24A7852-937D-4D9D-9086-8B976FE979E8}\ProgID
- Creates the key HKEY_CLASSES_ROOT\CLSID\{F24A7852-937D-4D9D-9086-8B976FE979E8}\Programmable

- String Default is set to "{17689671-9839-463D-9DAC-2800AA4D74F5}" in HKEY_CLASSES_ROOT\CLSID\{F24A7852-937D-4D9D-9086-8B976FE979E8}\TypeLib
- String Default is set to "OdClientControl.OdClientSecurityDatabase" in HKEY_CLASSES_ROOT\CLSID\{F24A7852-937D-4D9D-9086-8B976FE979E8}\VersionIndependentProgID
- String Default is set to "OdysseyEngine Class" in HKEY_CLASSES_ROOT\CLSID\{C4BB5277-BC02-4DE6-846F-E18A50095DF6}
- String Default is set to "[INSTALLDIR]odService.dll" and String ThreadingModel is set to "Free" in HKEY_CLASSES_ROOT\CLSID\{C4BB5277-BC02-4DE6-846F-E18A50095DF6}\InprocServer32
- String Default is set to "OdService.OdysseyEngine.1" in HKEY_CLASSES_ROOT\CLSID\{C4BB5277-BC02-4DE6-846F-E18A50095DF6}\ProgID
- String Default is set to "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}" in HKEY_CLASSES_ROOT\CLSID\{C4BB5277-BC02-4DE6-846F-E18A50095DF6}\TypeLib
- String Default is set to "OdService.OdysseyEngine" in HKEY_CLASSES_ROOT\CLSID\{C4BB5277-BC02-4DE6-846F-E18A50095DF6}\VersionIndependentProgID
- String Default is set to "ConfigUI Class" in HKEY_CLASSES_ROOT\CLSID\{473D6B6A-AA07-4098-8546-1A15D020F9EE}
- String Default is set to "[INSTALLDIR]odClientMgrDialogs.dll" and String ThreadingModel is set to "Both" in HKEY_CLASSES_ROOT\CLSID\{473D6B6A-AA07-4098-8546-1A15D020F9EE}\InprocServer32
- String Default is set to "odClientMgrDialogs.ConfigUI.1" in HKEY_CLASSES_ROOT\CLSID\{473D6B6A-AA07-4098-8546-1A15D020F9EE}\ProgID
- String Default is set to "{EDA6503C-E7A9-4BD0-9A2A-79466C41FF88}" in HKEY_CLASSES_ROOT\CLSID\{473D6B6A-AA07-4098-8546-1A15D020F9EE}\TypeLib
- String Default is set to "odClientMgrDialogs.ConfigUI" in HKEY_CLASSES_ROOT\CLSID\{473D6B6A-AA07-4098-8546-1A15D020F9EE}\VersionIndependentProgID
- String Default is set to "OdServiceDialogMgr Class" in HKEY_CLASSES_ROOT\CLSID\{71486BF6-30BD-4D9B-AD24-3AF8854B7D1E}
- String Default is set to "[INSTALLDIR]odServiceDialogs.dll" and String ThreadingModel is set to "Both" in HKEY_CLASSES_ROOT\CLSID\{71486BF6-30BD-4D9B-AD24-3AF8854B7D1E}\InprocServer32

- String Default is set to “OdServiceDialogs.OdServiceDialogMgr.1” in HKEY_CLASSES_ROOT\CLSID\{71486BF6-30BD-4D9B-AD24-3AF8854B7D1E}\ProgID
- Creates the key HKEY_CLASSES_ROOT\CLSID\{71486BF6-30BD-4D9B-AD24-3AF8854B7D1E}\Programmable
- String Default is set to “{2CC76071-B27F-49F1-9C3C-237DD3461A70}” in HKEY_CLASSES_ROOT\CLSID\{71486BF6-30BD-4D9B-AD24-3AF8854B7D1E}\TypeLib
- String Default is set to “OdServiceDialogs.OdServiceDialogMgr” in HKEY_CLASSES_ROOT\CLSID\{71486BF6-30BD-4D9B-AD24-3AF8854B7D1E}\VersionIndependentProgID
- String Default is set to “OdConsoleDialog Class” in HKEY_CLASSES_ROOT\OdConsole.OdConsoleDialog
- String Default is set to “{6B891951-71B6-405E-B9E8-3250FCF4BC51}” in HKEY_CLASSES_ROOT\OdConsole.OdConsoleDialog\CLSID
- String Default is set to “OdConsole.OdConsoleDialog.1” in HKEY_CLASSES_ROOT\OdConsole.OdConsoleDialog\CurVer
- String Default is set to “OdConsoleDialog Class” in HKEY_CLASSES_ROOT\OdConsole.OdConsoleDialog.1
- String Default is set to “{6B891951-71B6-405E-B9E8-3250FCF4BC51}” in HKEY_CLASSES_ROOT\OdConsole.OdConsoleDialog.1\CLSID
- String Default is set to “OdConsoleLogStream Class” in HKEY_CLASSES_ROOT\OdConsole.OdConsoleLogStream
- String Default is set to “{CBBFB98A-CC29-440E-A62F-ADD5C69D25DC}” in HKEY_CLASSES_ROOT\OdConsole.OdConsoleLogStream\CLSID
- String Default is set to “OdConsole.OdConsoleLogStream.1” in HKEY_CLASSES_ROOT\OdConsole.OdConsoleLogStream\CurVer
- String Default is set to “OdConsoleLogStream Class” in HKEY_CLASSES_ROOT\OdConsole.OdConsoleLogStream.1
- String Default is set to “{CBBFB98A-CC29-440E-A62F-ADD5C69D25DC}” in HKEY_CLASSES_ROOT\OdConsole.OdConsoleLogStream.1\CLSID
- Creates the key HKEY_CLASSES_ROOT\TypeLib
- Creates the key HKEY_CLASSES_ROOT\TypeLib\{6D396288-D452-4869-9895-4EEE4D3C8CF4}
- String Default is set to “odConsole 1.0 Type Library” in HKEY_CLASSES_ROOT\TypeLib\{6D396288-D452-4869-9895-4EEE4D3C8CF4}\1.0

- Creates the key HKEY_CLASSES_ROOT\TypeLib\{6D396288-D452-4869-9895-4EEE4D3C8CF4}\1.0\0
- String Default is set to “[CommonFilesFolder]Funk Software\odConsole.dll” in HKEY_CLASSES_ROOT\TypeLib\{6D396288-D452-4869-9895-4EEE4D3C8CF4}\1.0\0\win32
- String Default is set to “0” in HKEY_CLASSES_ROOT\TypeLib\{6D396288-D452-4869-9895-4EEE4D3C8CF4}\1.0\FLAGS
- String Default is set to “[CommonFilesFolder]Funk Software\” in HKEY_CLASSES_ROOT\TypeLib\{6D396288-D452-4869-9895-4EEE4D3C8CF4}\1.0\HELPPDIR
- Creates the key HKEY_CLASSES_ROOT\Interface
- String Default is set to “IConfigUI” in HKEY_CLASSES_ROOT\Interface\{56618E3B-08D0-41ED-B0E4-0DC9CBC5624A}
- String Default is set to “{EDA6503C-E7A9-4BD0-9A2A-79466C41FF88}” and String Version is set to “1.0” in HKEY_CLASSES_ROOT\Interface\{56618E3B-08D0-41ED-B0E4-0DC9CBC5624A}\TypeLib
- String Default is set to “{00020424-0000-0000-C000-000000000046}” in HKEY_CLASSES_ROOT\Interface\{56618E3B-08D0-41ED-B0E4-0DC9CBC5624A}\ProxyStubClsid
- String Default is set to “{00020424-0000-0000-C000-000000000046}” in HKEY_CLASSES_ROOT\Interface\{56618E3B-08D0-41ED-B0E4-0DC9CBC5624A}\ProxyStubClsid32
- String Default is set to “IOdGinaDialog” in HKEY_CLASSES_ROOT\Interface\{B5717F1F-4373-432D-9089-6370558A24B6}
- String Default is set to “{00020424-0000-0000-C000-000000000046}” in HKEY_CLASSES_ROOT\Interface\{B5717F1F-4373-432D-9089-6370558A24B6}\ProxyStubClsid
- String Default is set to “{00020424-0000-0000-C000-000000000046}” in HKEY_CLASSES_ROOT\Interface\{B5717F1F-4373-432D-9089-6370558A24B6}\ProxyStubClsid32
- String Default is set to “{EDA6503C-E7A9-4BD0-9A2A-79466C41FF88}” in HKEY_CLASSES_ROOT\Interface\{B5717F1F-4373-432D-9089-6370558A24B6}\TypeLib
- Creates the key HKEY_CLASSES_ROOT\AppID
- String LocalService is set to “odClientService “ and String ServiceParameters is set to “-Service” in HKEY_CLASSES_ROOT\AppID\{9A2EB1DF-613A-4605-B94C-F6E9F1B83B53}
- String Default is set to “OdClientSecurityDatabase Class” in HKEY_CLASSES_ROOT\OdClientControl.OdClientSecurityDatabase

- String Default is set to "{F24A7852-937D-4D9D-9086-8B976FE979E8}" in HKEY_CLASSES_ROOT\OdClientControl.OdClientSecurityDatabase\CLSID
- String Default is set to "OdClientControl.OdClientSecurityDatabase.1" in HKEY_CLASSES_ROOT\OdClientControl.OdClientSecurityDatabase\CurVer
- String Default is set to "OdClientEngine Class" in HKEY_CLASSES_ROOT\OdClientControl.OdClientEngine.1
- String Default is set to "{0A3937EA-5A82-4363-A0CD-4245773C282C}" in HKEY_CLASSES_ROOT\OdClientControl.OdClientEngine.1\CLSID
- String Default is set to "OdClientConfigurationDatabase Class" in HKEY_CLASSES_ROOT\OdClientControl.OdClientConfigurationDatabase
- String Default is set to "{CF890798-FED6-49D3-A1F5-947BD485CC03}" in HKEY_CLASSES_ROOT\OdClientControl.OdClientConfigurationDatabase\CLSID
- String Default is set to "OdClientControl.OdClientConfigurationDatabase.1" in HKEY_CLASSES_ROOT\OdClientControl.OdClientConfigurationDatabase\CurVer
- String Default is set to "OdClientSecurityDatabase Class" in HKEY_CLASSES_ROOT\OdClientControl.OdClientSecurityDatabase.1
- String Default is set to "{F24A7852-937D-4D9D-9086-8B976FE979E8}" in HKEY_CLASSES_ROOT\OdClientControl.OdClientSecurityDatabase.1\CLSID
- String Default is set to "OdClientEngine Class" in HKEY_CLASSES_ROOT\OdClientControl.OdClientEngine
- String Default is set to "{0A3937EA-5A82-4363-A0CD-4245773C282C}" in HKEY_CLASSES_ROOT\OdClientControl.OdClientEngine\CLSID
- String Default is set to "OdClientControl.OdClientEngine.1" in HKEY_CLASSES_ROOT\OdClientControl.OdClientEngine\CurVer
- String Default is set to "OdClientConfigurationDatabase Class" in HKEY_CLASSES_ROOT\OdClientControl.OdClientConfigurationDatabase.1
- String Default is set to "{CF890798-FED6-49D3-A1F5-947BD485CC03}" in HKEY_CLASSES_ROOT\OdClientControl.OdClientConfigurationDatabase.1\CLSID
- String Default is set to "OdysseyEngine Class" in HKEY_CLASSES_ROOT\OdService.OdysseyEngine
- String Default is set to "{C4BB5277-BC02-4DE6-846F-E18A50095DF6}" in HKEY_CLASSES_ROOT\OdService.OdysseyEngine\CLSID
- String Default is set to "OdService.OdysseyEngine.1" in HKEY_CLASSES_ROOT\OdService.OdysseyEngine\CurVer
- String Default is set to "OdysseyEngine Class" in HKEY_CLASSES_ROOT\OdService.OdysseyEngine.1

- String Default is set to “{C4BB5277-BC02-4DE6-846F-E18A50095DF6}” in HKEY_CLASSES_ROOT\OdService.OdysseyEngine.1\CLSID
- String Default is set to “OdServiceDialogMgr Class” in HKEY_CLASSES_ROOT\OdServiceDialogs.OdServiceDialogMgr
- String Default is set to “{71486BF6-30BD-4D9B-AD24-3AF8854B7D1E}” in HKEY_CLASSES_ROOT\OdServiceDialogs.OdServiceDialogMgr\CLSID
- String Default is set to “OdServiceDialogs.OdServiceDialogMgr.1” in HKEY_CLASSES_ROOT\OdServiceDialogs.OdServiceDialogMgr\CurVer
- String Default is set to “OdServiceDialogMgr Class” in HKEY_CLASSES_ROOT\OdServiceDialogs.OdServiceDialogMgr.1
- String Default is set to “{71486BF6-30BD-4D9B-AD24-3AF8854B7D1E}” in HKEY_CLASSES_ROOT\OdServiceDialogs.OdServiceDialogMgr.1\CLSID
- Creates the key HKEY_CURRENT_USER\Software\Funk Software, Inc.
- Creates the key HKEY_CURRENT_USER\Software\Funk Software, Inc.\Odyssey
- String OdTray.exe is set to “[INSTALLDIR]OdTray.exe” in HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\Run
- Creates the key HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\App Paths
- String Default is set to “[INSTALLDIR]odConfig.exe” and String Path is set to “[INSTALLDIR];[CommonFilesFolder]Funk Software” in HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\App Paths\odConfig.exe
- String Default is set to “[INSTALLDIR]OdTray.exe” and String Path is set to “[INSTALLDIR];[CommonFilesFolder]Funk Software” in HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\App Paths\OdTray.exe
- String Default is set to “[INSTALLDIR]odLoginScript.exe” and String Path is set to “[INSTALLDIR];[CommonFilesFolder]Funk Software” in HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\App Paths\odLoginScript.exe
- Creates the key HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\Control Panel
- Creates the key HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\Control Panel\Extended Properties
- Dword %SystemRoot%\System32\odcpl.cpl is set to “00000003” in HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\Windows\CurrentVersion\Control Panel\Extended Properties\{305CA226-D286-468e-B848-2B2E8E697B74} 2

- String `commonFiles` is set to “[CommonFilesFolder]Funk Software” in `HKEY_LOCAL_MACHINE\SOFTWARE\Funk Software, Inc.`
- Creates the key `HKEY_LOCAL_MACHINE\SOFTWARE\Funk Software, Inc.\odyssey`
- String `programDirectory` is set to “[INSTALLDIR]” in `HKEY_LOCAL_MACHINE\SOFTWARE\Funk Software, Inc.\odyssey\client`
- Creates the key `HKEY_LOCAL_MACHINE\SOFTWARE\Funk Software, Inc.\odyssey\client\configuration`
- String `nwgina.dll` is set to “1” in `HKEY_LOCAL_MACHINE\SOFTWARE\Funk Software, Inc.\odyssey\client\configuration\ginaDLLs`
- Creates the key `HKEY_LOCAL_MACHINE\SOFTWARE\Funk Software, Inc.\odyssey\client\configuration\options`
- String `useOdyssey` is set to “[USEODYSSEY]” and string `nameType` is set to “[NAMETYPE]” in `HKEY_LOCAL_MACHINE\SOFTWARE\Funk Software, Inc.\odyssey\client\configuration\options\nwGina`
- Creates the key `HKEY_LOCAL_MACHINE\SOFTWARE\Juniper Networks`
- Sets the following values in `HKEY_LOCAL_MACHINE\SOFTWARE\Juniper Networks\Common Files`:
 - String `jnprnaapi`. Set to “C:\Program Files\Common Files\Juniper Networks\JNPRNA\jnprnaapi.dll”
 - String `nsStatsDump`. Set to “C:\Program Files\Common Files\Juniper Networks\JNPRNA\nsStatsDump.exe”
 - String `jnprvamgr`. Set to “C:\Program Files\Common Files\Juniper Networks\JNPRNA\jnprvamgr.dll”
- Creates the key `HKEY_LOCAL_MACHINE\SOFTWARE\Juniper Networks, Inc.`
- Creates the key `HKEY_LOCAL_MACHINE\SOFTWARE\Juniper Networks, Inc.\InstallData`
- Sets the following strings in `HKEY_LOCAL_MACHINE\SOFTWARE\Juniper Networks, Inc.\InstallData\Odyssey Access Client`. Values are based on the installation:
 - `ProductName`
 - `Manufacturer`
 - `LICENSEKEY`
 - `IS30DAY`
 - `OEMBRANDING`
 - `OEMLICENSEKEY`

- EEINSTALL
- CommonFiles
- ISReleaseFlags
- INSTALLDIR
- PRECONFIGUREEXE
- PRECONFIGUREDMSI
- SETUPEXEDIR
- SUPPORTDIR
- DRIVERS_DIR
- CertTempDirectory
- INSTALLGINA
- odFIPSDriverReturn

The Odyssey Access Client sets the log file location, size and filename in:

HKLM\Software\Juniper Networks\Logging

The installData registry keys are located in:

HKLM\Software\Juniper Networks\InstallData\Juniper Odyssey Access Client

Client-side Log file location

You can enable or disable client-side logs through the **System > Log/Monitoring > Client Logs > Settings** tab of the Web console. When you enable logging, Odyssey Access Client adds log files to the following location:

C:\Documents and Settings\All Users\Application Data\Juniper Networks\Logging\

Log files installed by the Odyssey Access Client

The Odyssey Access Client adds service log files to: C:\Documents and Settings\All Users\Application Data\Juniper Networks\Logging\debuglog.log and C:\Documents and Settings\All Users\Application Data\Juniper Networks\UAC Agent\OACInstall.log.

Installing with Active-X or Java

If the IVE successfully installs Active-X or Java, the Odyssey Access Client installs the following additional files in the C:\Documents and Settings\<username>\Application Data\Juniper Networks\Setup directory:

- dsmmf.exe
- dsmmfres_de.dll
- dsmmfres_es.dll
- dsmmfres_fr.dll

- dsmmfres_ja.dll
- dsmmfres_ko.dll
- dsmmfres_zh.dll
- dsmmfres_zh_cn.dll
- JuniperSetupApp.exe
- JuniperSetupDLL.dll
- NeoterisSetup.ocx
- setupResource_de.dll
- setupResource_en.dll
- setupResource_es.dll
- setupResource_fr.dll
- setupResource_ja.dll
- setupResource_ko.dll
- setupResource_zh.dll
- setupResource_zh_cn.dll
- string_de.properties
- string_en.properties
- string_es.properties
- string_fr.properties
- string_ja.properties
- string_ko.properties
- string_zh.properties
- string_zh_cn.properties
- uninstall.exe
- versionInfo.ini

When running the installer, the following files are added to C:\Windows\Downloaded Program Files:

- JuniperSetup.inf
- JuniperSetup.ocx

- string_en.properties
- string_de.properties
- string_es.properties
- string_fr.properties
- string_ja.properties
- string_ko.properties
- string_zh.properties
- string_zh_cn.properties

Registry modifications

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Code Store Database\Distribution\Units\{E5F5D008-DD2C-4D32-977D-1A0ADF03058B}:

- DWord SystemComponent. Set to "0x0000000"
- String Installer. Set to "MSICD"

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Code Store Database\Distribution\Units\{E5F5D008-DD2C-4D32-977D-1A0ADF03058B}\Contains\Files:

- String \$WINDIR\Downloaded Program Files\string_zh_cn.properties. Set to ""
- String \$WINDIR\Downloaded Program Files\string_zh.properties. Set to ""
- String \$WINDIR\Downloaded Program Files\string_ko.properties. Set to ""
- String \$WINDIR\Downloaded \Program Files\string_ja.properties. Set to ""
- String \$WINDIR\Downloaded Program Files\string_fr.properties. Set to ""
- String \$WINDIR\Downloaded Program Files\string_es.properties. Set to ""
- String \$WINDIR\Downloaded Program Files\string_de.properties. Set to ""
- String \$WINDIR\Downloaded Program Files\string_en.properties. Set to ""
- String \$WINDIR\Downloaded Program Files\JuniperSetup.ocx. Set to ""

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Code Store Database\Distribution Units\{E5F5D008-DD2C-4D32-977D-1A0ADF03058B}\DownloadInformation:

- String CODEBASE. Set to "https://juniper.net/dana-cached/setup/JuniperSetupSP1.cab"
- String INF. Set to "\$WINDIR\Downloaded Program Files\JuniperSetup.INF"

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Code Store Database\Distribution Units\{E5F5D008-DD2C-4D32-977D-1A0ADF03058B}\InstalledVersion:

- String "". Set to "\${NEO_PRODUCT_VERSION}"
- String LastModified. Set to "Thu, 14 Sep 2006 07:32:24 GMT"

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\ModuleUsage\\${WINDIR}\Downloaded Program Files\JuniperSetup.ocx:

- String .Owner. Set to "{E5F5D008-DD2C-4D32-977D-1A0ADF03058B}"
- String {E5F5D008-DD2C-4D32-977D-1A0ADF03058B}. Set to ""

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\ModuleUsage\\${WINDIR}\Downloaded Program Files/string_en.properties:

- String .Owner. Set to "{E5F5D008-DD2C-4D32-977D-1A0ADF03058B}"
- String {E5F5D008-DD2C-4D32-977D-1A0ADF03058B}. Set to ""

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\ModuleUsage\\${WINDIR}\Downloaded Program Files/string_de.properties:

- String .Owner. Set to "{E5F5D008-DD2C-4D32-977D-1A0ADF03058B}"
- String {E5F5D008-DD2C-4D32-977D-1A0ADF03058B}. Set to ""

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\ModuleUsage\\${WINDIR}\Downloaded Program Files/string_es.properties:

- String .Owner. Set to "{E5F5D008-DD2C-4D32-977D-1A0ADF03058B}"
- String {E5F5D008-DD2C-4D32-977D-1A0ADF03058B}. Set to ""

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\ModuleUsage\\${WINDIR}\Downloaded Program Files/string_fr.properties:

- String .Owner. Set to "{E5F5D008-DD2C-4D32-977D-1A0ADF03058B}"
- String {E5F5D008-DD2C-4D32-977D-1A0ADF03058B}. Set to ""

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\ModuleUsage\\${WINDIR}\Downloaded Program Files/string_ja.properties:

- String .Owner. Set to "{E5F5D008-DD2C-4D32-977D-1A0ADF03058B}"
- String {E5F5D008-DD2C-4D32-977D-1A0ADF03058B}. Set to ""

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\ModuleUsage\\${WINDIR}/Downloaded Program Files/string_ko.properties:

- String .Owner. Set to "{E5F5D008-DD2C-4D32-977D-1A0ADF03058B}"
- String {E5F5D008-DD2C-4D32-977D-1A0ADF03058B}. Set to ""

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\ModuleUsage\\${WINDIR}/Downloaded Program Files/string_zh.properties:

- String .Owner. Set to "{E5F5D008-DD2C-4D32-977D-1A0ADF03058B}"
- String {E5F5D008-DD2C-4D32-977D-1A0ADF03058B}. Set to ""

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\ModuleUsage\\${WINDIR}/Downloaded Program Files/string_zh_cn.properties:

- String .Owner. Set to "{E5F5D008-DD2C-4D32-977D-1A0ADF03058B}"
- String {E5F5D008-DD2C-4D32-977D-1A0ADF03058B}. Set to ""

The Odyssey Access Client sets the following values in HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\SharedDLLs:

- Dword \$WINDIR\Downloaded Program Files\string_zh_cn.properties. Set to "0x00000001"
- Dword \$WINDIR\Downloaded Program Files\string_zh.properties. Set to "0x00000001"
- Dword \$WINDIR\Downloaded Program Files\string_ko.properties. Set to "0x00000001"
- Dword \$WINDIR\Downloaded Program Files\string_ja.properties. Set to "0x00000001"
- Dword \$WINDIR\Downloaded Program Files\string_fr.properties. Set to "0x00000001"
- Dword \$WINDIR\Downloaded Program Files\string_es.properties. Set to "0x00000001"
- Dword \$WINDIR\Downloaded Program Files\string_de.properties. Set to "0x00000001"
- Dword \$WINDIR\Downloaded Program Files\string_en.properties. Set to "0x00000001"
- Dword \$WINDIR\Downloaded Program Files\JuniperSetup.ocx. Set to "0x00000001"

Odyssey Access Client on Windows Vista 64-bit

In Windows Vista (64-bit), the Odyssey Access Client installs the following files on the client in the Program Files (x86)\Common Files\Funk Software directory:

- dcfDOM.dll
- dcfLibrary.dll
- odCert_M.dll
- odConsole.dll
- odLib_OSSL.dll
- odShadow.dll

Odyssey Access Client on Windows Vista 64-bit

In Windows Vista (64-bit), the Odyssey Access Client installs the following files on the client in the Program Files (x86)\Common Files\Juniper Networks\JNPRNA directory:

- install.log
- jnprna.cat
- jnprna.inf
- jnprna.sys
- jnprna_m.cat
- jnprna_m.inf
- jnprnaapi.dll
- jnprnaNetInstall.dll
- jnprnaNetInstallTest.log
- jnprva.cat
- jnprva.inf
- jnprva.sys
- jnprvamgr.cat
- jnprvamgr.dll
- jnprvamgr.inf
- jnprvamgr.sys
- nsStatsDump.exe

- uninst.exe
- versionInfo.ini

Odyssey Access Client on Windows Vista 64-bit

In Windows Vista (64-bit), the Odyssey Access Client installs the following files on the client in the Program Files (x86)\Common Files\Juniper Networks\JNPRNA\x64 directory:

- jnprna.cat
- jnprna.inf
- jnprna.sys
- jnprna_m.cat
- jnprna_m.inf
- jnprnaNetInstall.dll
- jnprva.cat
- jnprva.inf
- jnprva.sys
- jnprvamgr.cat
- jnprvamgr.inf
- jnprvamgr.sys

Odyssey Access Client on Windows Vista 64-bit

In Windows Vista (64-bit), the Odyssey Access Client installs the following files on the client in the Program Files (x86)\Common Files\Juniper Networks\JSCDT directory:

- jnprShare.dll
- jnprShare.lock
- jnprShare.log
- jnprShare.txt

Odyssey Access Client on Windows Vista 64-bit

In Windows Vista (64-bit), the Odyssey Access Client installs the following files on the client in the Program Files (x86)\Common Files\Juniper Networks\JUNS directory:

- access.ini

- dsAccessService.exe
- dsInstallerService.dll
- dsLogService.dll
- install.log
- JuniperSetupClientOCX.exe
- JuniperSetupOCX.exe
- Uninstall.exe
- Uninstall.exe.manifest
- versionInfo.ini
- Odyssey Access Client on Windows Vista 64-bit

In Windows Vista (64-bit), the Odyssey Access Client installs the following files on the client in the **Program Files (x86)\Common Files\Juniper Networks\TNC Client** directory:

- AVManagerUnified.dll
- CAntiVirusCOM.dll
- CertAuthIMC.dll
- CFireWallCOM.dll
- dsHostCheckerResource_EN.dll
- dsnsisdll.dll
- dsWinClient.dll
- efc.dat
- EPCheck.dll
- FWManager.dll
- hcimc.dll
- install.log
- jsystemimc.dll
- jTnccNarProxy.dll
- jTnccService.exe
- msvcp60.dll

- OPSWATProcessesScanner.dll
- patchlinkimc.dll
- ShavlikIMC.dll
- SoHIMC.dll
- TNCC.dep
- UnifiedSDK.ini
- uninstall.exe
- versionInfo.inni

Odyssey Access Client on Windows Vista 64-bit

In Windows Vista (64-bit), the Odyssey Access Client installs the following files on the client in the Program Files (x86)\Common Files\Juniper Networks\Tunnel Manager directory:

- dsTMClient.dll
- dsTMService.dll
- dsTunnelManager.dll
- install.log
- TM.dep
- Uninstall.exe
- Uninstall.exe.manifest
- versionInfo.ini

Odyssey Access Client on Windows Vista 64-bit

In Windows Vista (64-bit), the Odyssey Access Client installs the following files on the client in the Program Files (x86)\Juniper Networks\Odyssey Access Client directory:

- AccessServiceComponent.exe
- ClientPreset.xml
- dsNetworkMonitor.dll
- epdiag.dll
- install.log
- InstallerHelper.dll

- JNPRCredProv.dll
- JNPRIhvExt.dll
- jnprnaInstall.exe
- JNPRSmartCardProv.dll
- msvcp60.dll
- odClient.chm
- odClientAdministrator.exe
- odClientControl.dll
- odClientMgr.exe
- odClientMgrDialogs.dll
- odClientResource0009.dll
- odClientService.exe
- Odcp1.cpl
- odGinaLibrary.dll
- odGinaLibrary64.dll
- odjpaservice.dll
- odLogin.dll
- odLoginScript.exe
- odPush.dat
- odSCard.dll
- odService.dll
- odServiceDialogs.dll
- odServiceResource0009.dll
- OdTray.exe
- odyEvent.dll
- odyGina.dll
- odyNwLgXctl.ocx
- readme.txt

- TnccSetup.exe
- TunnelManagerComponent.exe
- uninst.exe
- versionInfo.ini

Odyssey Access Client on Windows Vista 64-bit

In Windows Vista (64-bit), the Odyssey Access Client installs the following files on the client in the Program Files (x86)\Juniper Networks\UAC Agent directory:

- UACAgent.dep
- versionInfo.ini

Odyssey Access Client on Windows Vista 64-bit

In Windows Vista (64-bit), the Odyssey Access Client installs the following files on the client in the Windows\System32 directory:

- JNPRCredProv.dll
- JNPRIhvExt.dll
- JNPRSmartCardProv.dll
- odGinaLibrary64.dll

Odyssey Access Client on Windows Vista 64-bit

In Windows Vista (64-bit), the Odyssey Access Client installs the following files on the client in the Windows\SysWOW64 directory:

- odGinaLibrary.dll
- odSendPacket.dll

Odyssey Access Client on Windows Vista 64-bit

In Windows Vista (64-bit), the Odyssey Access Client installs the following files on the client in the Windows\winsxs\amd64_microsoft.vc80.crt_1fc8b3b9a1e18e3b_8.0.50727.762_none_c905be8887838ff2 directory:

- amd64_Microsoft.VC80.CRT_1fc8b3b9a1e18e3b_8.0.50727.762_x-ww_9d1c6ce0.cat
- amd64_Microsoft.VC80.CRT_1fc8b3b9a1e18e3b_8.0.50727.762_x-ww_9d1c6ce0.manifest
- msvcm80.dll
- msvcp80.dll

- msvcr80.dll

Odyssey Access Client on Windows Vista 64-bit

In Windows Vista (64-bit), the Odyssey Access Client installs the following files on the client in the Windows\winsxs\amd64_policy.8.0.microsoft.vc80.crt_1fc8b3b9a1e18e3b_8.0.50727.762_none_49e66f4952a1b53b directory:

- 8.0.50727.762.cat
- 8.0.50727.762.policy

Odyssey Access Client on Windows Vista 64-bit Registry modifications

The following modifications to Windows 64-bit include:

[HKEY_CLASSES_ROOT\DcfDOM.DomFactory]

@ = "DomFactory Class"

[HKEY_CLASSES_ROOT\DcfDOM.DomFactory\CLSID]

@ = "{99DD0F0F-FA5F-11D2-8F6B-008029ED5244}"

[HKEY_CLASSES_ROOT\DcfDOM.DomFactory\CurVer]

@ = "DcfDOM.DomFactory.1"

[HKEY_CLASSES_ROOT\DcfDOM.DomFactory.1]

@ = "DomFactory Class"

[HKEY_CLASSES_ROOT\DcfDOM.DomFactory.1\CLSID]

@ = "{99DD0F0F-FA5F-11D2-8F6B-008029ED5244}"

[HKEY_CLASSES_ROOT\OdCert_M.OdCertLib]

@ = "OdCertLib Class"

[HKEY_CLASSES_ROOT\OdCert_M.OdCertLib\CLSID]

@ = "{D5639173-6BDA-4EA9-85A3-2F1771F4756F}"

[HKEY_CLASSES_ROOT\OdCert_M.OdCertLib\CurVer]

@ = "OdCert_M.OdCertLib.1"

[HKEY_CLASSES_ROOT\OdCert_M.OdCertLib.1]

@ = "OdCertLib Class"

[HKEY_CLASSES_ROOT\OdCert_M.OdCertLib.1\CLSID]

```

@ = "{D5639173-6BDA-4EA9-85A3-2F1771F4756F}"
[HKEY_CLASSES_ROOT\OdClientControl.OdClientConfigurationDatabase]

@ = "OdClientConfigurationDatabase Class"
[HKEY_CLASSES_ROOT\OdClientControl.OdClientConfigurationDatabase\CLSID]

@ = "{CF890798-FED6-49D3-A1F5-947BD485CC03}"
[HKEY_CLASSES_ROOT\OdClientControl.OdClientConfigurationDatabase\CurVer]

@ = "OdClientControl.OdClientConfigurationDatabase.1"
[HKEY_CLASSES_ROOT\OdClientControl.OdClientConfigurationDatabase.1]

@ = "OdClientConfigurationDatabase Class"
[HKEY_CLASSES_ROOT\OdClientControl.OdClientConfigurationDatabase.1\CLSID]

@ = "{CF890798-FED6-49D3-A1F5-947BD485CC03}"
[HKEY_CLASSES_ROOT\OdClientControl.OdClientEngine]

@ = "OdClientEngine Class"
[HKEY_CLASSES_ROOT\OdClientControl.OdClientEngine\CLSID]

@ = "{0A3937EA-5A82-4363-A0CD-4245773C282C}"
[HKEY_CLASSES_ROOT\OdClientControl.OdClientEngine\CurVer]

@ = "OdClientControl.OdClientEngine.1"
[HKEY_CLASSES_ROOT\OdClientControl.OdClientEngine.1]

@ = "OdClientEngine Class"
[HKEY_CLASSES_ROOT\OdClientControl.OdClientEngine.1\CLSID]

@ = "{0A3937EA-5A82-4363-A0CD-4245773C282C}"
[HKEY_CLASSES_ROOT\OdClientControl.OdClientSecurityDatabase]

@ = "OdClientSecurityDatabase Class"
[HKEY_CLASSES_ROOT\OdClientControl.OdClientSecurityDatabase\CLSID]

@ = "{F24A7852-937D-4D9D-9086-8B976FE979E8}"
[HKEY_CLASSES_ROOT\OdClientControl.OdClientSecurityDatabase\CurVer]

@ = "OdClientControl.OdClientSecurityDatabase.1"
[HKEY_CLASSES_ROOT\OdClientControl.OdClientSecurityDatabase.1]

```

@ = "OdClientSecurityDatabase Class"

[HKEY_CLASSES_ROOT\OdClientControl.OdClientSecurityDatabase.1\CLSID]

@ = "{F24A7852-937D-4D9D-9086-8B976FE979E8}"

[HKEY_CLASSES_ROOT\odClientMgrDialogs.ConfigUI]

@ = "ConfigUI Class"

[HKEY_CLASSES_ROOT\odClientMgrDialogs.ConfigUI\CLSID]

@ = "{473D6B6A-AA07-4098-8546-1A15D020F9EE}"

[HKEY_CLASSES_ROOT\odClientMgrDialogs.ConfigUI\CurVer]

@ = "odClientMgrDialogs.ConfigUI.1"

[HKEY_CLASSES_ROOT\odClientMgrDialogs.ConfigUI.1]

@ = "ConfigUI Class"

[HKEY_CLASSES_ROOT\odClientMgrDialogs.ConfigUI.1\CLSID]

@ = "{473D6B6A-AA07-4098-8546-1A15D020F9EE}"

[HKEY_CLASSES_ROOT\OdClientService.OdysseyClientService]

@ = "OdysseyClientService Class"

[HKEY_CLASSES_ROOT\OdClientService.OdysseyClientService\CLSID]

@ = "{52E64D2C-C33D-42ED-8C82-1EB83CFD9C4E}"

[HKEY_CLASSES_ROOT\OdClientService.OdysseyClientService\CurVer]

@ = "OdClientService.OdysseyClientService.1"

[HKEY_CLASSES_ROOT\OdClientService.OdysseyClientService.1]

@ = "OdysseyClientService Class"

[HKEY_CLASSES_ROOT\OdClientService.OdysseyClientService.1\CLSID]

@ = "{52E64D2C-C33D-42ED-8C82-1EB83CFD9C4E}"

[HKEY_CLASSES_ROOT\OdClientService.OdysseyServiceSupplicantMgr]

@ = "OdysseyServiceSupplicantMgr Class"

[HKEY_CLASSES_ROOT\OdClientService.OdysseyServiceSupplicantMgr\CLSID]

@ = "{801B616C-A8CE-4EDC-A7F0-AFE343D44A77}"

[HKEY_CLASSES_ROOT\OdClientService.OdysseyServiceSupplicantMgr\CurVer]

```

@ = "OdClientService.OdysseyServiceSupplicantMgr.1"
[HKEY_CLASSES_ROOT\OdClientService.OdysseyServiceSupplicantMgr.1]

@ = "OdysseyServiceSupplicantMgr Class"
[HKEY_CLASSES_ROOT\OdClientService.OdysseyServiceSupplicantMgr.1\CLSID]

@ = "{801B616C-A8CE-4EDC-A7F0-AFE343D44A77}"
[HKEY_CLASSES_ROOT\OdConsole.OdConsoleDialog]

@ = "OdConsoleDialog Class"
[HKEY_CLASSES_ROOT\OdConsole.OdConsoleDialog\CLSID]

@ = "{6B891951-71B6-405E-B9E8-3250FCF4BC51}"
[HKEY_CLASSES_ROOT\OdConsole.OdConsoleDialog\CurVer]

@ = "OdConsole.OdConsoleDialog.1"
[HKEY_CLASSES_ROOT\OdConsole.OdConsoleDialog.1]

@ = "OdConsoleDialog Class"
[HKEY_CLASSES_ROOT\OdConsole.OdConsoleDialog.1\CLSID]

@ = "{6B891951-71B6-405E-B9E8-3250FCF4BC51}"
[HKEY_CLASSES_ROOT\OdConsole.OdConsoleLogStream]

@ = "OdConsoleLogStream Class"
[HKEY_CLASSES_ROOT\OdConsole.OdConsoleLogStream\CLSID]

@ = "{CBBFB98A-CC29-440E-A62F-ADD5C69D25DC}"
[HKEY_CLASSES_ROOT\OdConsole.OdConsoleLogStream\CurVer]

@ = "OdConsole.OdConsoleLogStream.1"
[HKEY_CLASSES_ROOT\OdConsole.OdConsoleLogStream.1]

@ = "OdConsoleLogStream Class"
[HKEY_CLASSES_ROOT\OdConsole.OdConsoleLogStream.1\CLSID]

@ = "{CBBFB98A-CC29-440E-A62F-ADD5C69D25DC}"
[HKEY_CLASSES_ROOT\Odjpaservice.odAgentManager]

@ = "odAgentManager Class"
[HKEY_CLASSES_ROOT\Odjpaservice.odAgentManager\CLSID]

```

```

@ = "{083FC947-9EB1-42AF-8D97-07250E139585}"
[HKEY_CLASSES_ROOT\Odjpaservice.odAgentManager\CurVer]
@ = "Odjpaservice.odAgentManager.1"
[HKEY_CLASSES_ROOT\Odjpaservice.odAgentManager.1]
@ = "odAgentManager Class"
[HKEY_CLASSES_ROOT\Odjpaservice.odAgentManager.1\CLSID]
@ = "{083FC947-9EB1-42AF-8D97-07250E139585}"
[HKEY_CLASSES_ROOT\Odjpaservice.odCBConfig]
@ = "odCBConfig Class"
[HKEY_CLASSES_ROOT\Odjpaservice.odCBConfig\CLSID]
@ = "{15691C1F-702D-467A-86DC-F527C5F0D615}"
[HKEY_CLASSES_ROOT\Odjpaservice.odCBConfig.1]
@ = "odCBConfig Class"
[HKEY_CLASSES_ROOT\Odjpaservice.odCBConfig.1\CLSID]
@ = "{15691C1F-702D-467A-86DC-F527C5F0D615}"
[HKEY_CLASSES_ROOT\Odjpaservice.odCBMgr]
@ = "odCBMgr Class"
[HKEY_CLASSES_ROOT\Odjpaservice.odCBMgr\CLSID]
@ = "{E5A1613D-7813-4FEA-8FB3-850C7DECE9C5}"
[HKEY_CLASSES_ROOT\Odjpaservice.odCBMgr.1]
@ = "odCBMgr Class"
[HKEY_CLASSES_ROOT\Odjpaservice.odCBMgr.1\CLSID]
@ = "{E5A1613D-7813-4FEA-8FB3-850C7DECE9C5}"
[HKEY_CLASSES_ROOT\Odjpaservice.odIPSecConfig]
@ = "odIPSecConfig Class"
[HKEY_CLASSES_ROOT\Odjpaservice.odIPSecConfig\CLSID]
@ = "{5DD07C6B-9CE7-4C86-9784-439F52158448}"
[HKEY_CLASSES_ROOT\Odjpaservice.odIPSecConfig.1]

```

```

@ = "odIPSecConfig Class"
[HKEY_CLASSES_ROOT\Odjpaservice.odIPSecConfig.1\CLSID]
@ = "{5DD07C6B-9CE7-4C86-9784-439F52158448}"
[HKEY_CLASSES_ROOT\Odjpaservice.odIPSecMgr]
@ = "odIPSecMgr Class"
[HKEY_CLASSES_ROOT\Odjpaservice.odIPSecMgr\CLSID]
@ = "{BD15F01E-D575-42C9-8E88-C331391FDFA6}"
[HKEY_CLASSES_ROOT\Odjpaservice.odIPSecMgr.1]
@ = "odIPSecMgr Class"
[HKEY_CLASSES_ROOT\Odjpaservice.odIPSecMgr.1\CLSID]
@ = "{BD15F01E-D575-42C9-8E88-C331391FDFA6}"
[HKEY_CLASSES_ROOT\Odjpaservice.odIPSecRoute]
@ = "odIPSecRoute Class"
[HKEY_CLASSES_ROOT\Odjpaservice.odIPSecRoute\CLSID]
@ = "{749EDDC6-1AED-418C-A49C-0B5E67AF8A27}"
[HKEY_CLASSES_ROOT\Odjpaservice.odIPSecRoute.1]
@ = "odIPSecRoute Class"
[HKEY_CLASSES_ROOT\Odjpaservice.odIPSecRoute.1\CLSID]
@ = "{749EDDC6-1AED-418C-A49C-0B5E67AF8A27}"
[HKEY_CLASSES_ROOT\Odjpaservice.OdJuniperSetup]
@ = "OdJuniperSetup Class"
[HKEY_CLASSES_ROOT\Odjpaservice.OdJuniperSetup\CLSID]
@ = "{B911D855-FC84-4192-B0AF-B53CBAB83F54}"
[HKEY_CLASSES_ROOT\Odjpaservice.OdJuniperSetup\CurVer]
@ = "Odjpaservice.OdJuniperSetup.1"
[HKEY_CLASSES_ROOT\Odjpaservice.OdJuniperSetup.1]
@ = "OdJuniperSetup Class"
[HKEY_CLASSES_ROOT\Odjpaservice.OdJuniperSetup.1\CLSID]

```

```

@ = "{B911D855-FC84-4192-B0AF-B53CBAB83F54}"
[HKEY_CLASSES_ROOT\odjpaservice.OdMiniUnZip]

@ = "OdMiniUnZip Class"
[HKEY_CLASSES_ROOT\odjpaservice.OdMiniUnZip\CLSID]

@ = "{DF7A8815-F320-48ED-A219-DAAFB3C1FBD1}"
[HKEY_CLASSES_ROOT\odjpaservice.OdMiniUnZip\CurVer]

@ = "odjpaservice.OdMiniUnZip.1"
[HKEY_CLASSES_ROOT\odjpaservice.OdMiniUnZip.1]

@ = "OdMiniUnZip Class"
[HKEY_CLASSES_ROOT\odjpaservice.OdMiniUnZip.1\CLSID]

@ = "{DF7A8815-F320-48ED-A219-DAAFB3C1FBD1}"
[HKEY_CLASSES_ROOT\Odjpaservice.OdMiniZip]

@ = "OdMiniZip Class"
[HKEY_CLASSES_ROOT\Odjpaservice.OdMiniZip\CLSID]

@ = "{0462122E-567A-48D1-B585-A851C120537D}"
[HKEY_CLASSES_ROOT\Odjpaservice.OdMiniZip\CurVer]

@ = "Odjpaservice.OdMiniZip.1"
[HKEY_CLASSES_ROOT\Odjpaservice.OdMiniZip.1]

@ = "OdMiniZip Class"
[HKEY_CLASSES_ROOT\Odjpaservice.OdMiniZip.1\CLSID]

@ = "{0462122E-567A-48D1-B585-A851C120537D}"
[HKEY_CLASSES_ROOT\Odjpaservice.odSSLSession]

@ = "odSSLSession Class"
[HKEY_CLASSES_ROOT\Odjpaservice.odSSLSession\CLSID]

@ = "{4E5CA46B-FB17-4EC4-A676-0DD15230863D}"
[HKEY_CLASSES_ROOT\Odjpaservice.odSSLSession.1]

@ = "odSSLSession Class"
[HKEY_CLASSES_ROOT\Odjpaservice.odSSLSession.1\CLSID]

```

```

@ = "{4E5CA46B-FB17-4EC4-A676-0DD15230863D}"
[HKEY_CLASSES_ROOT\OdSCard.OdysseyAvailableSCardsFactory]
@ = "OdysseyAvailableSCardsFactory Class"
[HKEY_CLASSES_ROOT\OdSCard.OdysseyAvailableSCardsFactory\CLSID]
@ = "{03104BE6-BDDE-4FC3-B52B-869836FB408F}"
[HKEY_CLASSES_ROOT\OdSCard.OdysseyAvailableSCardsFactory\CurVer]
@ = "OdSCard.OdysseyAvailableSCardsFactory.1"
[HKEY_CLASSES_ROOT\OdSCard.OdysseyAvailableSCardsFactory.1]
@ = "OdysseyAvailableSCardsFactory Class"
[HKEY_CLASSES_ROOT\OdSCard.OdysseyAvailableSCardsFactory.1\CLSID]
@ = "{03104BE6-BDDE-4FC3-B52B-869836FB408F}"
[HKEY_CLASSES_ROOT\OdService.OdysseyEngine]
@ = "OdysseyEngine Class"
[HKEY_CLASSES_ROOT\OdService.OdysseyEngine\CLSID]
@ = "{C4BB5277-BC02-4DE6-846F-E18A50095DF6}"
[HKEY_CLASSES_ROOT\OdService.OdysseyEngine\CurVer]
@ = "OdService.OdysseyEngine.1"
[HKEY_CLASSES_ROOT\OdService.OdysseyEngine.1]
@ = "OdysseyEngine Class"
[HKEY_CLASSES_ROOT\OdService.OdysseyEngine.1\CLSID]
@ = "{C4BB5277-BC02-4DE6-846F-E18A50095DF6}"
[HKEY_CLASSES_ROOT\OdServiceDialogs.OdServiceDialogMgr]
@ = "OdServiceDialogMgr Class"
[HKEY_CLASSES_ROOT\OdServiceDialogs.OdServiceDialogMgr\CLSID]
@ = "{71486BF6-30BD-4D9B-AD24-3AF8854B7D1E}"
[HKEY_CLASSES_ROOT\OdServiceDialogs.OdServiceDialogMgr\CurVer]
@ = "OdServiceDialogs.OdServiceDialogMgr.1"
[HKEY_CLASSES_ROOT\OdServiceDialogs.OdServiceDialogMgr.1]

```

@ = "OdServiceDialogMgr Class"

[HKEY_CLASSES_ROOT\OdServiceDialogs.OdServiceDialogMgr.1\CLSID]

@ = "{71486BF6-30BD-4D9B-AD24-3AF8854B7D1E}"

[HKEY_CLASSES_ROOT\OdTnccService.OdTnccStub_Nar]

@ = "OdTnccStub_Nar Class"

[HKEY_CLASSES_ROOT\OdTnccService.OdTnccStub_Nar\CLSID]

@ = "{851F3E86-02D3-4388-84B7-8CC0C3104BB7}"

[HKEY_CLASSES_ROOT\OdTnccService.OdTnccStub_Nar\CurVer]

@ = "OdTnccService.OdTnccStub_Nar.1"

[HKEY_CLASSES_ROOT\OdTnccService.OdTnccStub_Nar.1]

@ = "OdTnccStub_Nar Class"

[HKEY_CLASSES_ROOT\OdTnccService.OdTnccStub_Nar.1\CLSID]

@ = "{851F3E86-02D3-4388-84B7-8CC0C3104BB7}"

[HKEY_CLASSES_ROOT\OdyNWLgxCtl.WirelessTab]

@ = "WirelessTab Class"

[HKEY_CLASSES_ROOT\OdyNWLgxCtl.WirelessTab\CLSID]

@ = "{28321A90-93A8-436A-BD0C-E25E11BB71F1}"

[HKEY_CLASSES_ROOT\OdyNWLgxCtl.WirelessTab\CurVer]

@ = "OdyNWLgxCtl.WirelessTab.1"

[HKEY_CLASSES_ROOT\OdyNWLgxCtl.WirelessTab.1]

@ = "WirelessTab Class"

[HKEY_CLASSES_ROOT\OdyNWLgxCtl.WirelessTab.1\CLSID]

@ = "{28321A90-93A8-436A-BD0C-E25E11BB71F1}"

[HKEY_CLASSES_ROOT\TypeLib\{17689671-9839-463D-9DAC-2800AA4D74F5}]

[HKEY_CLASSES_ROOT\TypeLib\{17689671-9839-463D-9DAC-2800AA4D74F5}\1.0]

@ = "odClientControl 1.0 Type Library"

[HKEY_CLASSES_ROOT\TypeLib\{17689671-9839-463D-9DAC-2800AA4D74F5}\1.0\0]

```
[HKEY_CLASSES_ROOT\TypeLib\{17689671-9839-463D-9DAC-2800AA4D74F5}\1.0\win32]
```

```
@ = "C:\\Program Files (x86)\\Juniper Networks\\Odyssey Access Client\\odClientControl.dll"
```

```
[HKEY_CLASSES_ROOT\TypeLib\{17689671-9839-463D-9DAC-2800AA4D74F5}\1.0\FLAGS]
```

```
@ = "0"
```

```
[HKEY_CLASSES_ROOT\TypeLib\{17689671-9839-463D-9DAC-2800AA4D74F5}\1.0\HELPPDIR]
```

```
@ = ""
```

```
[HKEY_CLASSES_ROOT\TypeLib\{2CC76071-B27F-49F1-9C3C-237DD3461A70}]
```

```
[HKEY_CLASSES_ROOT\TypeLib\{2CC76071-B27F-49F1-9C3C-237DD3461A70}\1.0]
```

```
@ = "odServiceDialogs 1.0 Type Library"
```

```
[HKEY_CLASSES_ROOT\TypeLib\{2CC76071-B27F-49F1-9C3C-237DD3461A70}\1.0\0]
```

```
[HKEY_CLASSES_ROOT\TypeLib\{2CC76071-B27F-49F1-9C3C-237DD3461A70}\1.0\win32]
```

```
@ = "C:\\Program Files (x86)\\Juniper Networks\\Odyssey Access Client\\odServiceDialogs.dll"
```

```
[HKEY_CLASSES_ROOT\TypeLib\{2CC76071-B27F-49F1-9C3C-237DD3461A70}\1.0\FLAGS]
```

```
@ = "0"
```

```
[HKEY_CLASSES_ROOT\TypeLib\{2CC76071-B27F-49F1-9C3C-237DD3461A70}\1.0\HELPPDIR]
```

```
@ = ""
```

```
[HKEY_CLASSES_ROOT\TypeLib\{3880EABE-2031-47EA-8BB7-8E9709A41D7A}]
```

```
[HKEY_CLASSES_ROOT\TypeLib\{3880EABE-2031-47EA-8BB7-8E9709A41D7A}\1.0]
```

```
@ = "odSCard 1.0 Type Library"
```

```
[HKEY_CLASSES_ROOT\TypeLib\{3880EABE-2031-47EA-8BB7-8E9709A41D7A}\1.0\0]
```

```
[HKEY_CLASSES_ROOT\TypeLib\{3880EABE-2031-47EA-8BB7-8E9709A41D7A}\1.0\win32]
```

```
@ = "C:\\Program Files (x86)\\Juniper Networks\\Odyssey Access Client\\odSCard.dll"
```

```
[HKEY_CLASSES_ROOT\\TypeLib\\{3880EABE-2031-47EA-8BB7-8E9709A41D7A}\\1.0\\FLAGS]
```

```
@ = "0"
```

```
[HKEY_CLASSES_ROOT\\TypeLib\\{3880EABE-2031-47EA-8BB7-8E9709A41D7A}\\1.0\\HELPPDIR]
```

```
@ = ""
```

```
[HKEY_CLASSES_ROOT\\TypeLib\\{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}]
```

```
[HKEY_CLASSES_ROOT\\TypeLib\\{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}\\1.0]
```

```
@ = "odService 1.0 Type Library"
```

```
[HKEY_CLASSES_ROOT\\TypeLib\\{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}\\1.0\\0]
```

```
[HKEY_CLASSES_ROOT\\TypeLib\\{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}\\1.0\\0\\win32]
```

```
@ = "C:\\Program Files (x86)\\Juniper Networks\\Odyssey Access Client\\odService.dll"
```

```
[HKEY_CLASSES_ROOT\\TypeLib\\{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}\\1.0\\FLAGS]
```

```
@ = "0"
```

```
[HKEY_CLASSES_ROOT\\TypeLib\\{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}\\1.0\\HELPPDIR]
```

```
@ = ""
```

```
[HKEY_CLASSES_ROOT\\TypeLib\\{9CDEA2D2-AD17-4BA7-9E69-CDA395508EDD}]
```

```
[HKEY_CLASSES_ROOT\\TypeLib\\{9CDEA2D2-AD17-4BA7-9E69-CDA395508EDD}\\1.0]
```

```
@ = "odjpaservice 1.0 Type Library"
```

```
[HKEY_CLASSES_ROOT\\TypeLib\\{9CDEA2D2-AD17-4BA7-9E69-CDA395508EDD}\\1.0\\0]
```

```
[HKEY_CLASSES_ROOT\\TypeLib\\{9CDEA2D2-AD17-4BA7-9E69-CDA395508EDD}\\1.0\\0\\win32]
```

```
@ = "C:\\Program Files (x86)\\Juniper Networks\\Odyssey Access Client\\odjpaservice.dll"
```

[HKEY_CLASSES_ROOT\TypeLib\{9CDEA2D2-AD17-4BA7-9E69-CDA395508EDD}\1.0\FLAGS]

@ = "0"

[HKEY_CLASSES_ROOT\TypeLib\{9CDEA2D2-AD17-4BA7-9E69-CDA395508EDD}\1.0\HELPPDIR]

@ = ""

[HKEY_CLASSES_ROOT\TypeLib\{D949A4C7-7F76-4052-A2D3-F3C40BE7ABE5}]

[HKEY_CLASSES_ROOT\TypeLib\{D949A4C7-7F76-4052-A2D3-F3C40BE7ABE5}\1.0]

@ = "odClientService 1.0 Type Library"

[HKEY_CLASSES_ROOT\TypeLib\{D949A4C7-7F76-4052-A2D3-F3C40BE7ABE5}\1.0\0]

[HKEY_CLASSES_ROOT\TypeLib\{D949A4C7-7F76-4052-A2D3-F3C40BE7ABE5}\1.0\0\win32]

@ = "C:\Program Files (x86)\Juniper Networks\Odyssey Access Client\odClientService.exe"

[HKEY_CLASSES_ROOT\TypeLib\{D949A4C7-7F76-4052-A2D3-F3C40BE7ABE5}\1.0\FLAGS]

@ = "0"

[HKEY_CLASSES_ROOT\TypeLib\{D949A4C7-7F76-4052-A2D3-F3C40BE7ABE5}\1.0\HELPPDIR]

@ = ""

[HKEY_CLASSES_ROOT\TypeLib\{EDA6503C-E7A9-4BD0-9A2A-79466C41FF88}]

[HKEY_CLASSES_ROOT\TypeLib\{EDA6503C-E7A9-4BD0-9A2A-79466C41FF88}\1.0]

@ = "odcConfigUI 1.0 Type Library"

[HKEY_CLASSES_ROOT\TypeLib\{EDA6503C-E7A9-4BD0-9A2A-79466C41FF88}\1.0\0]

[HKEY_CLASSES_ROOT\TypeLib\{EDA6503C-E7A9-4BD0-9A2A-79466C41FF88}\1.0\0\win32]

@ = "C:\Program Files (x86)\Juniper Networks\Odyssey Access Client\odClientMgrDialogs.dll"

[HKEY_CLASSES_ROOT\TypeLib\{EDA6503C-E7A9-4BD0-9A2A-79466C41FF88}\1.0\FLAGS]

@ = "0"

[HKEY_CLASSES_ROOT\TypeLib\{EDA6503C-E7A9-4BD0-9A2A-79466C41FF88}\1.0\HELPDIR]

@ = ""

[HKEY_CLASSES_ROOT\TypeLib\{FFC6CC98-F00D-44E3-9B33-40B442258468}]

[HKEY_CLASSES_ROOT\TypeLib\{FFC6CC98-F00D-44E3-9B33-40B442258468}\1.0]

@ = "odyNWLgxCtl 1.0 Type Library"

[HKEY_CLASSES_ROOT\TypeLib\{FFC6CC98-F00D-44E3-9B33-40B442258468}\1.0\0]

[HKEY_CLASSES_ROOT\TypeLib\{FFC6CC98-F00D-44E3-9B33-40B442258468}\1.0\0\win32]

@ = "C:\Program Files (x86)\Juniper Networks\Odyssey Access Client\odyNwLgXctl.ocx"

[HKEY_CLASSES_ROOT\TypeLib\{FFC6CC98-F00D-44E3-9B33-40B442258468}\1.0\FLAGS]

@ = "0"

[HKEY_CLASSES_ROOT\TypeLib\{FFC6CC98-F00D-44E3-9B33-40B442258468}\1.0\HELPDIR]

@ = ""

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{0462122E-567A-48D1-B585-A851C120537D}]

@ = "OdMiniZip Class"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{0462122E-567A-48D1-B585-A851C120537D}\InprocServer32]

@ = "C:\Program Files (x86)\Juniper Networks\Odyssey Access Client\odjpaservice.dll"

"ThreadingModel" = "Apartment"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{0462122E-567A-48D1-B585-A851C120537D}\ProgID]

@ = "Odjpaservice.OdMiniZip.1"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{0462122E-567A-48D1-B585-A851C120537D}\TypeLib]

@ = "{9CDEA2D2-AD17-4BA7-9E69-CDA395508EDD}"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{0462122E-567A-48D1-B585-A851C120537D}\VersionIndependentProgID]

@ = "Odjpaservice.OdMiniZip"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{083FC947-9EB1-42AF-8D97-07250E139585}]

@ = "odAgentManager Class"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{083FC947-9EB1-42AF-8D97-07250E139585}\InprocServer32]

@ = "C:\Program Files (x86)\Juniper Networks\Odyssey Access Client\odjpaservice.dll"

"ThreadingModel" = "Free"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{083FC947-9EB1-42AF-8D97-07250E139585}\ProgID]

@ = "Odjpaservice.odAgentManager.1"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{083FC947-9EB1-42AF-8D97-07250E139585}\Programmable]

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{083FC947-9EB1-42AF-8D97-07250E139585}\TypeLib]

@ = "{9CDEA2D2-AD17-4BA7-9E69-CDA395508EDD}"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{083FC947-9EB1-42AF-8D97-07250E139585}\VersionIndependentProgID]

@ = "Odjpaservice.odAgentManager"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{0A3937EA-5A82-4363-A0CD-4245773C282C}]

@ = "OdClientEngine Class"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{0A3937EA-5A82-4363-A0CD-4245773C282C}\InprocServer32]

@ = "C:\Program Files (x86)\Juniper Networks\Odyssey Access Client\odClientControl.dll"

"ThreadingModel" = "Both"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{0A3937EA-5A82-4363-A0CD-4245773C282C}\ProgID]

@ = "OdClientControl.OdClientEngine.1"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{0A3937EA-5A82-4363-A0CD-4245773C282C}\Programmable]

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{0A3937EA-5A82-4363-A0CD-4245773C282C}\TypeLib]

@ = "{17689671-9839-463D-9DAC-2800AA4D74F5}"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{0A3937EA-5A82-4363-A0CD-4245773C282C}\VersionIndependentProgID]

@ = "OdClientControl.OdClientEngine"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{15691C1F-702D-467A-86DC-F527C5F0D615}]

@ = "odCBConfig Class"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{15691C1F-702D-467A-86DC-F527C5F0D615}\InprocServer32]

@ = "C:\Program Files (x86)\Juniper Networks\Odyssey Access Client\odjpaservice.dll"

"ThreadingModel" = "both"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{15691C1F-702D-467A-86DC-F527C5F0D615}\ProgID]

@ = "Odjpaservice.odCBConfig.1"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{15691C1F-702D-467A-86DC-F527C5F0D615}\VersionIndependentProgID]

@ = "Odjpaservice.odCBConfig"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{DF7A8815-F320-48ED-A219-DAAFB3C1FBD1}]

@ = "OdMiniUnZip Class"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{DF7A8815-F320-48ED-A219-DAAFB3C1FBD1}\InprocServer32]

@ = "C:\Program Files (x86)\Juniper Networks\Odyssey Access Client\odjpaservice.dll"

"ThreadingModel" = "Apartment"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{DF7A8815-F320-48ED-A219-DAAFB3C1FBD1}\ProgID]

@ = "odjpaservice.OdMiniUnZip.1"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{DF7A8815-F320-48ED-A219-DAAFB3C1FBD1}\Programmable]

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{DF7A8815-F320-48ED-A219-DAAFB3C1FBD1}\TypeLib]

@ = "{}"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{DF7A8815-F320-48ED-A219-DAAFB3C1FBD1}\VersionIndependentProgID]

@ = "odjpaservice.OdMiniUnZip"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{E5A1613D-7813-4FEA-8FB3-850C7DECE9C5}]

@ = "odCBMgr Class"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{E5A1613D-7813-4FEA-8FB3-850C7DECE9C5}\InprocServer32]

@ = "C:\Program Files (x86)\Juniper Networks\Odyssey Access Client\odjpaservice.dll"

"ThreadingModel" = "both"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{E5A1613D-7813-4FEA-8FB3-850C7DECE9C5}\ProgID]

@ = "Odjpaservice.odCBMgr.1"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{E5A1613D-7813-4FEA-8FB3-850C7DECE9C5}\VersionIndependentProgID]

@ = "Odjpaservice.odCBMgr"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{F24A7852-937D-4D9D-9086-8B976FE979E8}]

@ = "OdClientSecurityDatabase Class"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{F24A7852-937D-4D9D-9086-8B976FE979E8}\InprocServer32]

@ = "C:\Program Files (x86)\Juniper Networks\Odyssey Access Client\odClientControl.dll"

"ThreadingModel" = "Both"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{F24A7852-937D-4D9D-9086-8B976FE979E8}\ProgID]

@ = "OdClientControl.OdClientSecurityDatabase.1"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{F24A7852-937D-4D9D-9086-8B976FE979E8}\Programmable]

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{F24A7852-937D-4D9D-9086-8B976FE979E8}\TypeLib]

@ = "{17689671-9839-463D-9DAC-2800AA4D74F5}"

[HKEY_CLASSES_ROOT\Wow6432Node\CLSID\{F24A7852-937D-4D9D-9086-8B976FE979E8}\VersionIndependentProgID]

@ = "OdClientControl.OdClientSecurityDatabase"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{00FAB823-2BBF-4A96-A397-AA2863F7215B}]

@ = "IOdysseySupplicantStatus"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{00FAB823-2BBF-4A96-A397-AA2863F7215B}\ProxyStubClsid]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{00FAB823-2BBF-4A96-A397-AA2863F7215B}\ProxyStubClsid32]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{00FAB823-2BBF-4A96-A397-AA2863F7215B}\TypeLib]

@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"

"Version" = "1.0"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{13F6B17E-7057-4860-BBB2-4180A5EA4854}]

@ = "IOdysseySupplicantStatistics"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{13F6B17E-7057-4860-BBB2-4180A5EA4854}\ProxyStubClsid]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{13F6B17E-7057-4860-BBB2-4180A5EA4854}\ProxyStubClsid32]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{13F6B17E-7057-4860-BBB2-4180A5EA4854}\TypeLib]

@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{2046CC8A-A639-4BB0-9DCD-AF9BFC85EE41}]
```

```
@ = "IOdysseyIC"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{2046CC8A-A639-4BB0-9DCD-AF9BFC85EE41}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{2046CC8A-A639-4BB0-9DCD-AF9BFC85EE41}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{2046CC8A-A639-4BB0-9DCD-AF9BFC85EE41}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{20FCF5F9-590D-46ED-89C4-261AB89459CF}]
```

```
@ = "IOdysseySCardLogObserver"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{20FCF5F9-590D-46ED-89C4-261AB89459CF}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{20FCF5F9-590D-46ED-89C4-261AB89459CF}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{20FCF5F9-590D-46ED-89C4-261AB89459CF}\TypeLib]
```

```
@ = "{3880EABE-2031-47EA-8BB7-8E9709A41D7A}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{3ABAD91D-A962-436A-8F18-090DFE37854E}]
```

```
@ = "IOdysseyTunnel"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{3ABAD91D-A962-436A-8F18-090DFE37854E}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{3ABAD91D-A962-436A-8F18-090DFE37854E}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{3ABAD91D-A962-436A-8F18-090DFE37854E}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{3EE4AFC6-0386-4E73-8D7D-74419EE1EBCA}]
```

```
@ = "IOdysseyTunnels"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{3EE4AFC6-0386-4E73-8D7D-74419EE1EBCA}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{3EE4AFC6-0386-4E73-8D7D-74419EE1EBCA}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{3EE4AFC6-0386-4E73-8D7D-74419EE1EBCA}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{42982519-7168-4B1F-9244-7B61E6C23C7E}]
```

```
@ = "IOdysseyProvisionedPac"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{42982519-7168-4B1F-9244-7B61E6C23C7E}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{42982519-7168-4B1F-9244-7B61E6C23C7E}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{42982519-7168-4B1F-9244-7B61E6C23C7E}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

"Version" = "1.0"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{500782DE-C095-4BD1-9817-86523C9F0716}]

@ = "IOdysseyEngine"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{500782DE-C095-4BD1-9817-86523C9F0716}\ProxyStubClsid]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{500782DE-C095-4BD1-9817-86523C9F0716}\ProxyStubClsid32]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{500782DE-C095-4BD1-9817-86523C9F0716}\TypeLib]

@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"

"Version" = "1.0"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{572FCB98-154C-4FBC-BDA7-8B2A5A27E93D}]

@ = "IOdysseyEventObserver"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{572FCB98-154C-4FBC-BDA7-8B2A5A27E93D}\ProxyStubClsid]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{572FCB98-154C-4FBC-BDA7-8B2A5A27E93D}\ProxyStubClsid32]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{572FCB98-154C-4FBC-BDA7-8B2A5A27E93D}\TypeLib]

@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"

"Version" = "1.0"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{5BB9E8AB-AC6B-4482-AFDE-5A3F394A59B0}]

@ = "IOdysseySupplicantMgr_NAC"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{5BB9E8AB-AC6B-4482-AFDE-5A3F394A59B0}\ProxyStubClsid]

@ = "{00020424-0000-0000-C000-000000000046}"

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{5BB9E8AB-AC6B-4482-AFDE-5A3F394A59B0}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{5BB9E8AB-AC6B-4482-AFDE-5A3F394A59B0}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{63345CF1-4B80-4423-814D-01C810E730CD}]
```

```
@ = "_IOdysseySupplicantMgrEvents"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{63345CF1-4B80-4423-814D-01C810E730CD}\ProxyStubClsid]
```

```
@ = "{00020420-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{63345CF1-4B80-4423-814D-01C810E730CD}\ProxyStubClsid32]
```

```
@ = "{00020420-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{63345CF1-4B80-4423-814D-01C810E730CD}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{657310C1-7689-43F4-B6EE-28DE607920F3}]
```

```
@ = "IOdysseyTncStatus"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{657310C1-7689-43F4-B6EE-28DE607920F3}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{657310C1-7689-43F4-B6EE-28DE607920F3}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{657310C1-7689-43F4-B6EE-28DE607920F3}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{65CDC8C4-DAF7-48A4-A84B-2D20F70B4E5F}]

@ = "IOdysseySupplicantMgrContext"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{65CDC8C4-DAF7-48A4-A84B-2D20F70B4E5F}\ProxyStubClsid]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{65CDC8C4-DAF7-48A4-A84B-2D20F70B4E5F}\ProxyStubClsid32]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{65CDC8C4-DAF7-48A4-A84B-2D20F70B4E5F}\TypeLib]

@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"

"Version" = "1.0"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{6679A8B3-B560-4441-A6CE-B516667D59CC}]

@ = "IOdysseyBSSIDs"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{6679A8B3-B560-4441-A6CE-B516667D59CC}\ProxyStubClsid]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{6679A8B3-B560-4441-A6CE-B516667D59CC}\ProxyStubClsid32]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{6679A8B3-B560-4441-A6CE-B516667D59CC}\TypeLib]

@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"

"Version" = "1.0"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{6AB10DB0-A735-4DAE-8379-C69AF5BAC0C6}]

@ = "_IOdysseyICEvents"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{6AB10DB0-A735-4DAE-8379-C69AF5BAC0C6}\ProxyStubClsid]

@ = "{00020420-0000-0000-C000-000000000046}"

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{6AB10DB0-A735-4DAE-8379-
C69AF5BAC0C6}\ProxyStubClsid32]
```

```
@ = "{00020420-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{6AB10DB0-A735-4DAE-8379-
C69AF5BAC0C6}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{6CCED896-0F91-4D5B-A38D-
84041F787322}]
```

```
@ = "_IOdysseyUACMgrEvents"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{6CCED896-0F91-4D5B-A38D-
84041F787322}\ProxyStubClsid]
```

```
@ = "{00020420-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{6CCED896-0F91-4D5B-A38D-
84041F787322}\ProxyStubClsid32]
```

```
@ = "{00020420-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{6CCED896-0F91-4D5B-A38D-
84041F787322}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{707DD4EA-299C-40D2-829C-
0B9B4863FEC7}]
```

```
@ = "IOdysseyBSSID"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{707DD4EA-299C-40D2-829C-
0B9B4863FEC7}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{707DD4EA-299C-40D2-829C-
0B9B4863FEC7}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{707DD4EA-299C-40D2-829C-
0B9B4863FEC7}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Verion" = "1.0"
```

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{7BFFFA48-C4E0-469E-A772-B958D2BEAEB1}]

@ = "IOdysseyAvailableSCards"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{7BFFFA48-C4E0-469E-A772-B958D2BEAEB1}\ProxyStubClsid]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{7BFFFA48-C4E0-469E-A772-B958D2BEAEB1}\ProxyStubClsid32]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{7BFFFA48-C4E0-469E-A772-B958D2BEAEB1}\TypeLib]

@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"

"Version" = "1.0"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{7CB08D7A-7E84-4BD8-8436-58305B354A62}]

@ = "IOdysseyTunnelStatus"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{7CB08D7A-7E84-4BD8-8436-58305B354A62}\ProxyStubClsid]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{7CB08D7A-7E84-4BD8-8436-58305B354A62}\ProxyStubClsid32]

@ = "{00020424-0000-0000-C000-000000000046}"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{7CB08D7A-7E84-4BD8-8436-58305B354A62}\TypeLib]

@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"

"Version" = "1.0"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{827E5740-B06E-4A66-855C-2AE3FF8FFC2D}]

@ = "IOdysseyProvisionedPacs"

[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{827E5740-B06E-4A66-855C-2AE3FF8FFC2D}\ProxyStubClsid]

@ = "{00020424-0000-0000-C000-000000000046}"

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{827E5740-B06E-4A66-855C-2AE3FF8FFC2D}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{827E5740-B06E-4A66-855C-2AE3FF8FFC2D}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{83E52ED1-BA21-4D4C-AB17-65C513390F9B}]
```

```
@ = "IOdysseyClientPlugin"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{83E52ED1-BA21-4D4C-AB17-65C513390F9B}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{83E52ED1-BA21-4D4C-AB17-65C513390F9B}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{83E52ED1-BA21-4D4C-AB17-65C513390F9B}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{87DC252A-3F79-469C-808F-C65C8F0FA800}]
```

```
@ = "IOdysseySCCollection"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{87DC252A-3F79-469C-808F-C65C8F0FA800}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{87DC252A-3F79-469C-808F-C65C8F0FA800}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{87DC252A-3F79-469C-808F-C65C8F0FA800}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{8AFABAD7-EA05-48B2-B615-F9B8DE14056E}]
```

```
@ = "IOdysseyClientPlugins"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{8AFABAD7-EA05-48B2-B615-F9B8DE14056E}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{8AFABAD7-EA05-48B2-B615-F9B8DE14056E}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{8AFABAD7-EA05-48B2-B615-F9B8DE14056E}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{8C1B1268-C810-4CFC-9EED-FEFD4F6BC7FD}]
```

```
@ = "_IOdysseySupplicantEvents"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{8C1B1268-C810-4CFC-9EED-FEFD4F6BC7FD}\ProxyStubClsid]
```

```
@ = "{00020420-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{8C1B1268-C810-4CFC-9EED-FEFD4F6BC7FD}\ProxyStubClsid32]
```

```
@ = "{00020420-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{8C1B1268-C810-4CFC-9EED-FEFD4F6BC7FD}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{8D38CD9F-6AB2-4C60-A6C6-FD052D2610CA}]
```

```
@ = "IOdysseySCardEventObserver"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{8D38CD9F-6AB2-4C60-A6C6-FD052D2610CA}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{8D38CD9F-6AB2-4C60-A6C6-FD052D2610CA}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{8D38CD9F-6AB2-4C60-A6C6-FD052D2610CA}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{9A27F6B5-0C87-4CAA-8225-C0FB7D92FC20}]
```

```
@ = "IOdysseyAuthenticationStatus"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{9A27F6B5-0C87-4CAA-8225-C0FB7D92FC20}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{9A27F6B5-0C87-4CAA-8225-C0FB7D92FC20}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{9A27F6B5-0C87-4CAA-8225-C0FB7D92FC20}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{A5652786-A62D-483F-9F65-C7117E5E2F14}]
```

```
@ = "IOdysseySCard"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{A5652786-A62D-483F-9F65-C7117E5E2F14}\ProxyStubClsid]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{A5652786-A62D-483F-9F65-C7117E5E2F14}\ProxyStubClsid32]
```

```
@ = "{00020424-0000-0000-C000-000000000046}"
```

```
[HKEY_CLASSES_ROOT\Wow6432Node\Interface\{A5652786-A62D-483F-9F65-C7117E5E2F14}\TypeLib]
```

```
@ = "{52D8714F-D625-4BFA-AA2A-0DED6EC5746F}"
```

```
"Version" = "1.0"
```


