

JUNOScope 7.1 Software Release Notes

Release 7.1R4
28 November 2005
Part No. 530-012443-01
Revision 4

These release notes accompany Release 7.1R4 of the JUNOScope software. They describe the key features, documentation, and known problems with the software. The JUNOScope software is a network management application that provides router configuration management, inventory management, operational status, and troubleshooting tools for Juniper Networks J-series, M-series, and T-series routing platforms.

You can also find these release notes on the Juniper Networks Technical Publications Web page, which is located at <http://www.juniper.net/techpubs/>.

Contents	Release 7.1 Features	2
	Current Software Release	2
	Outstanding Issues	2
	Installation, Reinstallation, Upgrade, Deinstallation, and Uninstall Instructions	2
	JUNOScope Server System Requirements	3
	JUNOScope Client Workstation Requirements	3
	RADIUS Server Requirements	3
	Installing the JUNOScope Software	3
	Reconfiguring the JUNOScope Software	5
	Reinstalling or Upgrading the JUNOScope Software	5
	Deinstalling the JUNOScope Software	6
	Uninstalling the JUNOScope Software	6
	Product and Related Documentation	7
	How To Request Support	9
	Revision History	9

Release 7.1 Features

The following feature has been added to JUNOScope Release 7.1.

In addition to local password authentication in which the JUNOScope administrator sets up a username, password, and permissions for each user allowed to log in, the JUNOScope software now provides Remote Authentication Dial-In User Service (RADIUS) authentication. For RADIUS authentication, the administrator sets up one or more local template accounts or one remote template account in the JUNOScope software, with values that correspond to those in the RADIUS server so that RADIUS users get the appropriate permissions. The user with a RADIUS account is configured to get the same permissions as the user with a JUNOScope template account.

For more information about RADIUS authentication, see the *JUNOScope Software User Guide*.

Current Software Release

The current JUNOScope software release is Release 7.1R4. For information about installing the software release, see “Installation, Reinstallation, Upgrade, Deinstallation, and Uninstall Instructions” on page 2.

Outstanding Issues

This section lists outstanding issues with this release of the JUNOScope software. The identifier following the description is the tracking number in our bug database.

- Online Help** ■ The Related Topics links in each help topic do not work. As a workaround, see the *JUNOScope Software User Guide*. [PRJ36716]

Installation, Reinstallation, Upgrade, Deinstallation, and Uninstall Instructions

Before installing the JUNOScope software, ensure that your network meets the requirements described in the following sections:

- JUNOScope Server System Requirements on page 3
- JUNOScope Client Workstation Requirements on page 3
- RADIUS Server Requirements on page 3

To install, reconfigure, reinstall or upgrade, or deinstall the JUNOScope software, see the following sections:

- Installing the JUNOScope Software on page 3.
- Reconfiguring the JUNOScope Software on page 5.
- Reinstalling or Upgrading the JUNOScope Software on page 5
- Deinstalling the JUNOScope Software on page 6
- “Uninstalling the JUNOScope Software” on page 6

JUNOScope Server System Requirements

Before you install the JUNOScope software, ensure that the UNIX server workstation on which you install the software meets the minimum system requirements shown in Table 1.

Table 1: JUNOScope Software Minimum System Requirements

System	Minimum Requirement
Workstation	UltraSPARC III or equivalent
Operating system	Solaris 5.8 or later
RAM	1 GB
Disk space	750 MB

JUNOScope Client Workstation Requirements

Ensure that the client workstation from which you connect to the JUNOScope software is running either Microsoft Internet Explorer 6 or Netscape Navigator 6 or later with JavaScript enabled.

RADIUS Server Requirements

Ensure that the RADIUS server complies with RFC 2865, Remote Authentication Dial-In User Service.

Installing the JUNOScope Software

You can install the JUNOScope software in one of the following ways:

- Installing the JUNOScope Software from the CD-ROM on page 4
- Downloading the JUNOScope Software from the Software Download Page on page 4

To upgrade the JUNOScope software, see “Reinstalling or Upgrading the JUNOScope Software” on page 5.

For more information about installing the JUNOScope software, see the *JUNOScope Software User Guide*.

Installing the JUNOScope Software from the CD-ROM

To install the JUNOScope software from the product CD-ROM, follow these steps:

1. Insert the JUNOScope software CD-ROM into the CD-ROM drive of the server workstation.
2. Mount the CD-ROM.

If the volume management (volmgt) daemon, vold, is running on your server, the CD-ROM automatically mounts itself. To mount the CD-ROM manually, follow the procedure for your operating system.

3. Start the JUNOScope installation:

```
hostname% cdrom-mount-directory/jtk-installer install-directory
```

Replace *cdrom-mount-directory* with the directory on which the CD-ROM is mounted: /mnt, /cdrom, or /cdrom/JUNOScope, depending on your host setup.

Replace *install-directory* with the directory in which to install the JUNOScope software. If you do not specify an installation directory, the software is installed in the current directory.

For more information about installing the JUNOScope software, see the *JUNOScope Software User Guide*.

Downloading the JUNOScope Software from the Software Download Page

To download the JUNOScope software from the Juniper Networks Web site and start the JUNOScope installation, follow these steps:

1. Using a Web browser, go to the following location:

```
https://www.juniper.net/junos/swdist/encryption/index.htm
```

2. Log in to the Juniper Networks authentication system using the username (generally your e-mail address) and password supplied by a Juniper Networks representative.
3. Download the JUNOScope software to the server workstation.
4. Start the JUNOScope installation program:

```
hostname% download-directory/jtk-install-7.1R4.X-sunos5-sparc.sh install-directory
```

Replace *download-directory* with the directory into which you downloaded the JUNOScope software from the software download page.

jtk-install-7.1R4.X-sunos5-sparc.sh is the JUNOScope software file. Replace *X* with the software version to download.

Replace *install-directory* with the directory in which to install the JUNOScope software. If you do not specify an installation directory, the software is installed in the current directory.

Reconfiguring the JUNOScope Software

You can change the following JUNOScope software installation settings without rerunning the installation program. For more information about these settings, see the *JUNOScope Software User Guide*.

- The HTTPS and HTTP ports on which the JUNOScope Webserver should listen
- The port on which the JUNOScope server listens for control messages
- The HTTP port on which the JUNOScope report server should listen
- The Java Database Connectivity (JDBC) URL for accessing the JUNOScope database
- Debug logging
- Idle session timeout

You cannot change some settings, such as passwords.

To change JUNOScope software settings, use the following command:

```
hostname% <install-directory>/jtk/bin/jtk-setup.sh
```

Reinstalling or Upgrading the JUNOScope Software

The process for reinstalling or upgrading the JUNOScope software is the same as for installing the software. To install the JUNOScope software, see “Installing the JUNOScope Software from the CD-ROM” on page 4 or “Downloading the JUNOScope Software from the Software Download Page” on page 4.

To reinstall or upgrade JUNOScope software, you must use the same user ID as the one used for the currently installed software.

Deinstalling the JUNOScope Software

Deinstalling the JUNOScope software means that you can uninstall the current version of the JUNOScope software, then install an older one separately. The software features of the older version will apply, but the database contents, such as device configurations and Inventory Management System scan data, will be lost.

To deinstall the JUNOScope software, you must use the same user ID as the one used for the currently installed software.

To deinstall the JUNOScope software and install an older version, follow these steps:

1. Export all of the configurations stored in the CVS repository from the current version using Settings > Import/Export Data.
2. Uninstall the current JUNOScope software. (For more information about uninstalling JUNOScope, see the *JUNOScope Software User Guide*.)
3. Reinstall the older version of JUNOScope. See the installation instructions for the older version of JUNOScope.
4. Import all the configurations again using Settings > Import/Export Data.

Uninstalling the JUNOScope Software

To uninstall the JUNOScope software, follow these steps:

1. Stop the JUNOScope software and database by changing to the directory where you installed the JUNOScope software and typing the following command:

```
hostname% <install-directory>/jtk/rc.d/jtk stop
```

2. Remove the JUNOScope software by typing the following command:

```
hostname% rm -rf <install-directory>
```



WARNING: This command removes the JUNOScope <install-directory>, including all data.

Product and Related Documentation

Table 2 lists the software and hardware books for Juniper Networks routing platforms and describes the contents of each book.

Table 2: Juniper Networks Technical Documentation

Book	Description
JUNOS Configuration Guides	
<i>Feature Guide</i>	Provides a detailed explanation and configuration examples for several of the most complex features in the JUNOS software.
<i>System Basics</i>	Provides an overview of the JUNOS software and describes how to install and upgrade the software. This manual also describes how to configure system management functions and how to configure the chassis, including user accounts, passwords, and redundancy.
<i>MPLS Applications</i>	Provides an overview of traffic engineering concepts and describes how to configure traffic engineering protocols.
<i>Multicast Protocols</i>	Provides an overview of multicast concepts and describes how to configure multicast routing protocols.
<i>Network Interfaces and Class of Service</i>	Provides an overview of the network interface and class-of-service functions of the JUNOS software and describes how to configure the network interfaces on the routing platform.
<i>Network Management</i>	Provides an overview of network management concepts and describes how to configure various network management features, such as SNMP and accounting options.
<i>Policy Framework</i>	Provides an overview of policy concepts and describes how to configure routing policy, firewall filters, forwarding options, and cflowd.
<i>Routing Protocols</i>	Provides an overview of routing concepts and describes how to configure routing, routing instances, and unicast routing protocols.
<i>Services Interfaces</i>	Provides an overview of the services interfaces functions of the JUNOS software and describes how to configure the services interfaces on the routing platform.
<i>VPNs</i>	Provides an overview and describes how to configure Layer 2 and Layer 3 virtual private networks (VPNs), virtual private LAN service (VPLS), and Layer 2 circuits. Provides configuration examples.

Book	Description
JUNOS References	
<i>Network and Services Interfaces Command Reference</i>	Describes the JUNOS software operational mode commands you use to monitor and troubleshoot network and services interfaces on Juniper Networks J-series, M-series, and T-series routing platforms.
<i>Protocols, Class of Service, and System Basics Command Reference</i>	Describes the JUNOS software operational mode commands you use to monitor and troubleshoot most aspects of Juniper Networks J-series, M-series, and T-series routing platforms.
<i>System Log Messages Reference</i>	Describes how to access and interpret system log messages generated by JUNOS software modules and provides a reference page for each message.
JUNOScript API Documentation	
<i>JUNOScript API Guide</i>	Describes how to use the JUNOScript application programming interface (API) to monitor and configure Juniper Networks routing platforms.
<i>JUNOScript API Configuration Reference</i>	Provides a reference page for the configuration tags in the JUNOScript API.
<i>JUNOScript API Operational Reference</i>	Provides a reference page for the operational tags in the JUNOScript API.
JUNOS Comprehensive Index and Glossary	
<i>Comprehensive Index and Glossary</i>	Provides a complete index of all JUNOS software books and the <i>JUNOScript API Guide</i> . Also provides a comprehensive glossary.
Hardware Documentation	
<i>Hardware Guide</i>	Describes how to install, maintain, and troubleshoot routing platforms and components. Each platform has its own hardware guide.
<i>PIC Guide</i>	Describes the routing platform Physical Interface Cards (PICs). Each platform has its own PIC guide.
JUNOScope Documentation	
<i>JUNOScope User Guide</i>	Describes the JUNOScope software graphical user interface (GUI), how to install and administer the software, and how to use the software to manage routing platform configuration files and monitor routing platform operations.
J-series Services Router Documentation	
<i>J-series Services Router User Guide</i>	Contains instructions for installing, configuring, and managing a J-series Services Router. The guide explains how to prepare your site for installation, unpack and install the hardware, power on the router, configure secure routing, monitor network operations, and perform routine maintenance.
Release Notes	
<i>JUNOS Release Notes</i>	Summarize new features and known problems for a particular software release, provide corrections and updates to published JUNOS and JUNOScript manuals, provide information that might have been omitted from the manuals, and describe upgrade and downgrade procedures.
<i>Hardware Release Notes</i>	Describe the available documentation for the routing platform and the supported PICs, and summarize known problems with the hardware and accompanying software. Each platform has its own release notes.
<i>JUNOScope Software Release Notes</i>	Contain corrections and updates to the published JUNOScope manual, provide information that might have been omitted from the manual, and describe upgrade and downgrade procedures.
<i>J-series Services Router Release Notes</i>	Briefly describe the J-series Services Router features, identify known hardware problems, and provide upgrade and downgrade instructions.

How To Request Support

For technical support, open a support case using the Case Manager link at <http://www.juniper.net/support/> or call 1-888-314-JTAC (from the United States, Canada, or Mexico) or 1-408-745-9500 (from elsewhere).

For documentation issues, fill out the bug report form located at <https://www.juniper.net/techpubs/docbug/docbugreport.html>.

Revision History

11 February 2005—Revision 1, JUNOScope Release 7.1R1.

31 March 2005—Revision 2, JUNOScope Release 7.1R2.

29 July 2005—Revision 3, JUNOScope Release 7.1R3.

28 November 2005—Revision 4, JUNOScope Release 7.1R4.

Copyright © 2005, Juniper Networks, Inc. All rights reserved.

Juniper Networks, the Juniper Networks logo, NetScreen, NetScreen Technologies, the NetScreen logo, NetScreen-Global Pro, ScreenOS, and GigaScreen are registered trademarks of Juniper Networks, Inc. in the United States and other countries. The following are trademarks of Juniper Networks, Inc.: ERX, ESP, E-series, Instant Virtual Extranet, Internet Processor, J2300, J4300, J6300, J-Protect, J-series, J-Web, JUNOS, JUNOScope, JUNOScript, JUNOSe, M5, M7i, M10, M10i, M20, M40, M40e, M160, M320, M-series, MMD, NetScreen-5GT, NetScreen-5XP, NetScreen-5XT, NetScreen-25, NetScreen-50, NetScreen-204, NetScreen-208, NetScreen-500, NetScreen-5200, NetScreen-5400, NetScreen-IDP 10, NetScreen-IDP 100, NetScreen-IDP 500, NetScreen-Remote Security Client, NetScreen-Remote VPN Client, NetScreen-SA 1000 Series, NetScreen-SA 3000 Series, NetScreen-SA 5000 Series, NetScreen-SA Central Manager, NetScreen Secure Access, NetScreen-SM 3000, NetScreen-Security Manager, NMC-RX, SDX, Stateful Signature, T320, T640, T-series, and TX Matrix.

All other trademarks, service marks, registered trademarks, or registered service marks are the property of their respective owners. All specifications are subject to change without notice. Juniper Networks assumes no responsibility for any inaccuracies in this document. Juniper Networks reserves the right to change, modify, transfer, or otherwise revise this publication without notice.

