

Creating Managers Through the Enterprise Service Portal

To create managers through the enterprise service portal:

1. In the navigation pane of the enterprise service portal, click the object that you want the manager to control.
2. Click the **Managers** tab in the portal.

The portal displays the Manager's page for the object.

Figure 1: Manager's Page

Virneo Enterprise Portal

Log out

Navigation

ent-admin

SP

default

retailer-one

retailer-two

virtual-SP

Refresh

VPNs	Bandwidth & VPNs	Applications	Firewall	Schedules	Managers		
Login ID	Admin.	Modify sub.	Modify params.	Activate sub.	Modify VPNs	Password	
<input type="text"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="text"/>	Create

© Virneo 2004

3. Complete the fields in a new line of the table.

See Managers Fields in the Enterprise Service Portal.

4. Click **Create**.

The portal adds the new manager to the table.

Managers Fields in the Enterprise Service Portal

In the Managers tab of an enterprise service portal, you can modify the following fields to control privileges for managers.

Login ID

- Name that this manager uses to access the enterprise portal.
- Value—Text string
- Guidelines—Login IDs for enterprises must be unique within the whole enterprise; retailer-level login IDs must be unique to the retailer.
- Default—No value
- Example—Operator1

Admin.

- Whether or not the manager has complete control over managers, subscribers, subscriptions, substitutions, subscription sessions, and virtual private networks (VPNs) for this object and its subordinate objects.
- Value
 - Enabled—Checked box
 - Disabled—White box
- Default—Disabled

Modify sub.

- Whether or not the manager has complete control over subscriptions and subscription sessions for this object and its subordinate objects.
- Value
 - Enabled—Checked box
 - Disabled—White box
- Default—Disabled

Modify params.

- Whether or not the manager can configure substitutions in subscribers and subscriptions for this object and its subordinate objects.
- Value
 - Enabled—Checked box
 - Disabled—White box
- Default—Disabled

Activate sub.

- Whether or not the manager can configure automatic activation of subscriptions and manually activate and deactivate subscription sessions for this object and its subordinate objects.
- Value

- Enabled—Checked box
- Disabled—White box
- Default—Disabled

Modify VPNs

- Whether or not the manager can modify, export, and cancel the export of VPNs in the enterprise.
- Value
 - Enabled—Checked box
 - Disabled—White box
- Guidelines—This field appears only if the service provider configures the portal to display the VPN features.
- Default—Disabled

Password

- Password that this manager uses to access the enterprise portal.
- Value—Text string
- Default—No value
- Example—Secret

