

Adding Enterprises (SRC CLI)

Use the following configuration statements to add an enterprise subscriber:

```
subscribers retailer name subscriber-folder folder-name enterprise name {  
    display-name display-name ;  
    accounting-user-id accounting-user-id ;  
    description description ;  
    scope [ scope... ] ;  
    substitution [ substitution... ] ;  
}
```

To add an enterprise subscriber:

1. From configuration mode, enter the enterprise subscriber configuration. In this procedure, ABCInc is the name of the enterprise subscriber.

```
user@host# edit subscribers retailer default subscriber-folder local enterprise  
ABCInc
```

2. (Optional) Configure the name that is displayed in enterprise management portals, if different from the enterprise name.

```
[edit subscribers retailer default subscriber-folder local enterprise ABCInc]  
user@host# set display-name display-name
```

3. (Optional) Configure the name that identifies the enterprise in accounting records.

```
[edit subscribers retailer default subscriber-folder local enterprise ABCInc]  
user@host# set accounting-user-id accounting-user-id
```

4. (Optional) Enter a description of the enterprise.

```
[edit subscribers retailer default subscriber-folder local enterprise ABCInc]  
user@host# set description description
```

5. (Optional) Assign service scopes to the enterprise.

```
[edit subscribers retailer default subscriber-folder local enterprise ABCInc]  
user@host# set scope [ scope... ]
```

6. (Optional) Configure the actual values for parameters associated with this enterprise.

```
[edit subscribers retailer default subscriber-folder local enterprise ABCInc]  
user@host# set substitution [ substitution... ]
```

7. (Optional) Verify your configuration.

```
[edit subscribers retailer default subscriber-folder local enterprise  
ABCInc]  
user@host# show  
display-name ABCInc;  
description "This enterprise is sample data for use with JUNOS routers."
```

The attached EntJunose scope contains enterprise services that are designed to work with JUNOSE.

```
scope [ EntJunose POP-Ottawa POP-Boca POP-Boston POP-Montreal ];
substitution [ "acct : network = 208.93.36.80 / 28" "eng : network =
208.93.36.64 / 28" ];
```

8. Configure an access subscription for the enterprise. (See Configuring Accesses (SRC CLI).)

Related Topics

- Adding Enterprises (C-Web Interface)
- Configuring Administrative Information for Enterprise Subscribers (SRC CLI)
- Enterprise Subscriber and Subscription Hierarchy
- Enterprise Subscriber Login Process
- Automatic Activation at Login