

## Configuring the Number of Concurrent Sessions and Concurrent Users for Infranet Controller Users (NSM Procedure)

You can limit the number of concurrent sessions and concurrent users for Infranet Controller users. A user who enters a URL to one of this realm's sign-in pages must meet any access management and concurrent user requirements specified for the authentication policy before the Infranet Controller presents the sign-in page to the user.

To configure the number of concurrent sessions and concurrent users for Infranet Controller users:

1. In the NSM navigation tree, select **Device Manager > Devices**.
2. Click the **Device tree** tab, and then double-click the Infranet Controller device for which you want to configure the number of concurrent sessions and concurrent users.
3. Click the **Configuration** tab. In the configuration tree, select the level at which you want to implement concurrent session restrictions. Then select:
  - **Administrators > Admin Realms > Select Realm > Authentication Policies > Limits** to configure the number of concurrent sessions for admin realms.
  - **Users > User Realms > Select Realm > Authentication Policies > Limits** to configure the number of concurrent sessions for user realms.



**NOTE:** The number of concurrent users can be configured only for user realms.

4. Add or modify settings as specified in Table 1 on page 1.
5. Click one:
  - **OK**—Saves the changes.
  - **Cancel**—Cancels the modifications.

**Table 1: Number of Concurrent Sessions and Concurrent Users for Infranet Controller User Configuration Details**

Option	Function	Your Action
Limit number of concurrent users	Limits the number of concurrent users on the realm.	Select this option to limit the number of concurrent users.
Guaranteed minimum	Specifies the number of users between zero (0) and the maximum number of concurrent users defined for the realm, or you can set the number to the maximum allowed by your license if there is no realm maximum.	Select or enter the number of users between zero (0) and the maximum number of concurrent users defined for the realm.

**Table 1: Number of Concurrent Sessions and Concurrent Users for Infranet Controller User Configuration Details** (continued)

Option	Function	Your Action
Limit the number of concurrent sessions per user	Specifies whether the number of concurrent sessions per user is limited.	Select this option to limit the number of concurrent sessions per user.
Session limit	Specifies the number of sessions permissible.  <b>NOTE:</b> You can configure this option only for user realms.	Specify the number of sessions permitted. By default, the number is 1 if the realm maximum is greater than 0; otherwise, the default is 0. The maximum number must be no greater than the maximum number of concurrent users for the realm.
Maximum	Specifies the maximum number of concurrent users.  <b>NOTE:</b> You can configure this option only for user realms.	Select or enter the maximum number of concurrent users permissible.

- Related Topics**
- Configuring Infranet Controller Source IP Access Restrictions (NSM Procedure)
  - Configuring Infranet Controller Browser Access Restrictions (NSM Procedure)
  - Configuring Infranet Controller Certificate Access Restrictions (NSM Procedure)
  - Configuring Infranet Controller Host Checker Access Restrictions (NSM Procedure)
  - Configuring Infranet Controller User Roles (NSM Procedure)
  - Creating and Configuring Infranet Controller Administrator Roles (NSM Procedure)