



JUNIPER NETWORKS STRM TECHNICAL NOTE

CHANGING NETWORK SETTINGS

PUBLISHED: 2009-06-29

This document provides information on changing network settings for the Console and non-Console systems when using CentOS-4 operating systems in your deployment including:

- [Changing Network Settings in an All-in-One Console](#)
- [Changing the Network Settings of a Console in a Multi-System Deployment](#)
- [Changing the Network Settings of a Non-Console in a Multi-System Deployment](#)

Changing Network Settings in an All-in-One Console

You can change the network settings in your All-In-One system. An All-In-One system has all STRM components, including the Administration Console, installed on one system.

To change the settings on the STRM Console:



Note: You must have a local connection to your Console before executing the script.

Step 1 Log in to the Console, as root.

Step 2 Enter the following command:

```
qchange_netsetup
```

The Configure STRM window appears.

Step 3 Using the up/down arrow keys to navigate the fields, change the necessary parameters:

- **Hostname** — Specify a fully qualified domain name as the system hostname.
- **IP Address** - Specify the IP address of the system.
- **Netmask** - Specify the network mask address for the system.
- **Gateway** - Specify the default gateway of the system.
- **Primary DNS** - Specify the primary DNS server.

- **Secondary DNS** - Optional. Specify the secondary DNS server.
- **Public IP** - Optional. Specify the public IP address of the server. The server uses this IP address to communicate with another server that belongs to a different network using Network Address Translation (NAT). NAT translates an IP address in one network to a different IP address in another network.
- **Email Server** - Specify the email server. If you do not have an email server, specify **localhost** in this field.

Step 4 Use the TAB key to navigate to the Finish option. Press **Enter**.



Note: A series of messages appear as STRM processes the requested changes. This is typically a one to two minute process.

Step 5 Enter the following commands to ensure proper permissions are enforced:

```
chown nobody:nobody /opt/qradar/conf/nva.conf
chown nobody:nobody /store/configservices/staging/globalconfig/nva.conf
chown nobody:nobody /store/configservices/deployed/globalconfig/nva.conf
```

Step 6 Enter the following command:

Exit

Changes are complete.

Changing the Network Settings of a Console in a Multi-System Deployment

To change the network settings in a multi-system deployment, you must remove all non-Console managed hosts from the deployment, change the network settings, re-add the managed host(s), and then re-assign the component(s).

You must perform this procedure in the following order:

- [Removing Non-Console Managed Hosts](#)
- [Changing the Network Settings](#)
- [Re-Adding Managed Host\(s\) and Re-Assigning the Components](#)



Note: This procedure requires you to use the Deployment Editor. For more information on using the Deployment Editor, see the STRM Administration Guide.

Removing Non-Console Managed Hosts

To remove non-Console managed hosts from your deployment, you must:

Step 1 Log in to STRM:

`https://<IP Address>`

Where `<IP Address>` is the IP address of the STRM system.

Username: `admin`

Password: `<root password>`

Where `<root password>` is the password assigned to STRM during the installation process.

- Step 2** In the main STRM Interface, click **Config**.
- Step 3** Click the deployment editor icon.
- Step 4** Click the **System View** tab.
- Step 5** Select the managed host you wish to delete.
- Step 6** Use the right mouse button (right-click) to access the menu, select **Remove host**. Repeat for each non-Console managed host until all hosts are deleted.
- Step 7** From the Administrative Console menu, select **Configurations > Deploy Configuration Changes**.
- Step 8** Exit from the Administration Console.



Note: If the Administration Console is still active on your system tray, use the right-mouse button (right-click) to access the menu and select **Exit**.

Changes are deployed.

Changing the Network Settings

To change the network settings, you must:

- Step 1** Log in to the Console as root.
- Step 2** Enter the following command:
`qchange_netsetup`
The Network Settings window appears.
- Step 3** Using the up/down arrow keys to navigate the fields, make the necessary changes to the following parameters:
 - **Hostname** — Specify a fully qualified domain name as the system hostname.
 - **IP Address** - Specify the IP address of the system.
 - **Netmask** - Specify the network mask address for the system.
 - **Gateway** - Specify the default gateway of the system.
 - **Primary DNS** - Specify the primary DNS server.
 - **Secondary DNS** - Optional. Specify the secondary DNS server.
 - **Public IP** - Optional. Specify the public IP address of the server. The server uses this IP address to communicate with another server that belongs to a different network using Network Address Translation (NAT). NAT translates an IP address in one network to a different IP address in another network.
 - **Email Server** - Specify the email server. If you do not have an email server, specify **localhost** in this field.
- Step 4** Use the TAB key to move to the Finish option. Press **Enter**.



Note: A series of messages appear as STRM processes the requested changes. This is typically a one to two minute process.

- Step 5** Enter the following commands to ensure proper permissions are enforced:

```
chown nobody:nobody /opt/qradar/conf/nva.conf
```

```
chown nobody:nobody /store/configservices/staging/globalconfig/nva.conf
chown nobody:nobody /store/configservices/deployed/globalconfig/nva.conf
```

Step 6 Enter the following command:

```
Exit
```

Changes are complete.

Re-Adding Managed Host(s) and Re-Assigning the Components

To re-add the managed host(s) and re-assign component(s), you must:

Step 1 Log in to STRM and access the System View in the Deployment Editor, as defined in [Step 1, Removing Non-Console Managed Hosts](#).

Re-add managed host(s) to your deployment.

Step 2 From the menu, select **Actions > Add a managed host**.

The Add a new host wizard appears.

Step 3 Click **Next**.

The Enter the host's IP window appears.

Step 4 Enter values for the parameters:

- **Enter the IP of the server or appliance to add** — Specify the IP address of the host you wish to add to your System View.
- **Enter the root password of the host** — Specify the root password for the host.
- **Confirm the root password of the host** — Specify the password again, for confirmation.

Step 5 Click **Next**.

Step 6 Click **Finish**.

Step 7 Re-assign all components to your non-Console managed host.

- a In the STRM Deployment Editor, click the **Flow View** or **Event View** tab.
- b Select the component you wish to re-assign to the managed host.
- c From the menu, select **Actions > Assign**



Note: You can also use the right mouse button (right-click) to access the Actions menu items.

The Assign Component wizard appears.

d From a Select a host drop-down list box, select the host you wish to re-assign to this component. Click **Next**.

e Click **Finish**.

Step 8 Repeat for each non-Console managed host until all hosts are re-added and re-assigned.

- Step 9** From the Administrative Console menu, select **Configurations > Deploy Configuration Changes**.

Changes are deployed.

Changing the Network Settings of a Non-Console in a Multi-System Deployment

To change the network settings of a non-Console in a multi-system deployment, you must remove all non-Console managed hosts from the deployment, change the network settings, re-add the managed host, and then re-assign the component(s).

You must perform this procedure in the following order:

- [Removing the Non-Console Managed Host](#)
- [Changing the Network Settings](#)
- [Re-Adding the Managed Host and Re-Assigning the Components](#)



Note: This procedure requires you to use the Deployment Editor. For more information on using the Deployment Editor, see the STRM Administration Guide.

Removing the Non-Console Managed Host

To remove non-Console managed host from your deployment, you must:

- Step 1** Log in to STRM:

https://<IP Address>

Where <IP Address> is the IP address of the STRM system.

Username: **admin**

Password: <root password>

Where <root password> is the password assigned to STRM during the installation process.

- Step 2** In the main STRM Interface, click **Config**.
- Step 3** In the main STRM Interface, click **Config**.
- Step 4** Click the deployment editor icon.
- Step 5** Click the **System View** tab.
- Step 6** Select the managed host you wish to delete.
- Step 7** Use the right mouse button (right-click) to access the menu, select **Remove host**.
- Step 8** From the Administrative Console menu, select **Configurations > Deploy Configuration Changes**.
- Step 9** Exit from the Administration Console.



Note: If the Administration Console is still active on your system tray, use the right-mouse button (right-click) to access the menu and select **Exit**.

Changes are deployed.

Changing the Network Settings

To change the network settings, you must:

Step 1 Log in to the non-Console as root.

Step 2 Enter the following command:

```
qchange_netsetup
```

The Network Settings window appears.

Step 3 Using the up/down arrow keys to navigate the fields, make the necessary changes to the following parameters:

- **Hostname** — Specify a fully qualified domain name as the system hostname.
- **IP Address** - Specify the IP address of the system.
- **Netmask** - Specify the network mask address for the system.
- **Gateway** - Specify the default gateway of the system.
- **Primary DNS** - Specify the primary DNS server.
- **Secondary DNS** - Optional. Specify the secondary DNS server.
- **Public IP** - Optional. Specify the public IP address of the server. The server uses this IP address to communicate with another server that belongs to a different network using Network Address Translation (NAT). NAT translates an IP address in one network to a different IP address in another network.
- **Email Server** - Specify the email server. If you do not have an email server, specify **localhost** in this field.

Step 4 Use the TAB key to move to the Finish option. Press **Enter**.



Note: A series of messages appear as STRM processes the requested changes. This is typically a one to two minute process.

Step 5 Enter the following commands to ensure proper permissions are enforced:

```
chown nobody:nobody /opt/qradar/conf/nva.conf
chown nobody:nobody /store/configservices/staging/globalconfig/nva.conf
chown nobody:nobody /store/configservices/deployed/globalconfig/nva.conf
```

Step 6 Enter the following command:

```
Exit
```

Changes are complete.

Re-Adding the Managed Host and Re-Assigning the Components

To re-add the managed host and re-assign component(s), you must:

Step 1 Log in to STRM and access the System View in the Deployment Editor, as defined in [Step 1, Removing the Non-Console Managed Host](#).

Re-add managed host to your deployment.

Step 2 From the menu, select **Actions > Add a managed host**.

The Add a new host wizard appears.

Step 3 Click **Next**.

The Enter the host's IP window appears.

Step 4 Enter values for the parameters:

- **Enter the IP of the server or appliance to add** — Specify the IP address of the host you wish to add to your System View.
- **Enter the root password of the host** — Specify the root password for the host.
- **Confirm the root password of the host** — Specify the password again, for confirmation.

Step 5 Click **Next**.

Step 6 Click **Finish**.

Step 7 Re-assign all components to your non-Console managed host.

- a In the STRM Deployment Editor, click the **Flow View** or **Event View** tab.
- b Select the component you wish to re-assign to the managed host.
- c From the menu, select **Actions > Assign**



Note: You can also use the right mouse button (right-click) to access the Actions menu items.

The Assign Component wizard appears.

- d From a Select a host drop-down list box, select the host you wish to re-assign to this component. Click **Next**.
- e Click **Finish**.

Step 8 From the Administrative Console menu, select **Configurations > Deploy Configuration Changes**.

Changes are deployed.

Juniper Networks, Inc.
1194 North Mathilda Avenue
Sunnyvale, CA 94089 USA

Copyright © 2008 Juniper Networks, Inc. All rights reserved. Juniper Networks and the Juniper Networks logo are registered trademarks of Juniper Networks Inc. in the United States and other countries. All other trademarks, service marks, registered trademarks, or registered service marks in this document are the property of Juniper Networks or their respective owners. All specifications are subject to change without notice. Juniper Networks assumes no responsibility for any inaccuracies in this document or for any obligation to update information in this document. Juniper Networks reserves the right to change, modify, transfer, or otherwise revise this publication without notice.