

Logging Out Simulated Subscribers with the CLI

You can view subscribers who are logged in and then log out subscribers who are accessible:

- Logging Out Subscribers by DN on page 1
- Logging Out Subscribers by IP Address on page 1
- Logging Out Subscribers by Login Name on page 2
- Logging Out Subscribers by Session ID on page 2

Logging Out Subscribers by DN

To log out subscribers who are accessible by DN:

1. Issue the **show sae subscribers dn** command to view the subscribers who are accessible by DN.
2. Issue the **request sae logout dn** command to log out all subscribers who are accessible by DN.
3. To log out specific subscribers, use the **filter** option and specify all or part of the DN for the subscribers that you want to log out.

```
user@host> request sae logout dn filter filter
```

4. To specify that no confirmation is requested before the software logs out the subscribers, use the **force** option.

```
user@host> request sae logout dn force  
user@host> request sae logout dn filter filter force
```

Logging Out Subscribers by IP Address

To log out subscribers who are accessible by IP address:

1. Issue the **show sae subscribers ip** command to view the subscribers who are accessible by IP address.
2. Issue the **request sae logout ip** command to log out all subscribers who are accessible by IP address.
3. To log out specific subscribers, use the **filter** option and specify the IP address for the subscribers that you want to log out.

```
user@host> request sae logout ip filter filter
```

4. To specify that no confirmation is requested before the software logs out the subscribers, use the **force** option.

```
user@host> request sae logout ip force  
user@host> request sae logout ip filter filter force
```

Logging Out Subscribers by Login Name

To log out subscribers who are accessible by login name:

1. Issue the **show sae subscribers login-name** command to view the subscribers accessible by login name.
2. Issue the **request sae logout login-name** command to log out all subscribers accessible by login name.
3. To log out specific subscribers, use the **filter** option and specify all or part of the login name for the subscribers that you want to log out.

```
user@host> request sae logout login-name filter filter
```

4. To specify that no confirmation is requested before the software logs out the subscribers, use the **force** option.

```
user@host> request sae logout login-name force  
user@host> request sae logout login-name filter filter force
```

Logging Out Subscribers by Session ID

To log out subscribers who are accessible by session ID:

1. Issue the **show sae subscribers session-id** command to view the subscribers accessible by session ID.
2. Issue the **request sae logout session-id** command to log out all subscribers accessible by session ID.
3. To log out specific subscribers, use the **filter** option and specify all or part of the session ID for the subscribers that you want to log out.

```
user@host> request sae logout session-id filter filter
```

4. To specify that no confirmation is requested before the software logs out the subscribers, use the **force** option.

```
user@host> request sae logout session-id force  
user@host> request sae logout session-id filter filter force
```