

Viewing JPS State

You can monitor the current state of the JPS by:

1. Viewing Performance Statistics for the JPS Interfaces on page 1
2. Viewing Network Connections for the Application Manager on page 1
3. Viewing Network Connections for the CMTS Device on page 1
4. Viewing Performance Statistics for the CMTS Locator on page 2
5. Viewing Message Handler Information on page 2

Viewing Performance Statistics for the JPS Interfaces

Purpose View performance statistics for JPS interfaces.

Action To view recent performance statistics for the application manager-to-policy server interface:

```
user@host> show jps statistics am
```

To view recent performance statistics for the policy server-to-CMTS interface:

```
user@host> show jps statistics cmts
```

To view recent performance statistics for the policy server-to-RKS interface:

```
user@host> show jps statistics rks
```

Viewing Network Connections for the Application Manager

Purpose View network connections for the application manager.

Action To view information about the current JPS network connections for all the application managers:

```
user@host> show jps statistics am connections
```

To view information about the current JPS network connections for a specific application manager:

```
user@host> show jps statistics am connections ip-address ip-address
```

Enter all or part of the IP address to list connections for all matching addresses.

Viewing Network Connections for the CMTS Device

Purpose View network connections for the CMTS Device.

Action To view information about the current JPS connections for all the CMTS devices:

```
user@host> show jps statistics cmts connections
```

To view information about the current JPS connections for a specific CMTS device:

```
user@host> show jps statistics cmts connections ip-address ip-address
```

Enter all or part of the IP address to list connections for all matching addresses.

Viewing Performance Statistics for the CMTS Locator

Purpose View information about the recent performance statistics for the CMTS locator.

Action user@host> **show jps statistics cmts-locator**

Viewing Message Handler Information

Purpose View message handler information.

Action To view information about the JPS message handler and message flows:

```
user@host> show jps statistics message-handler
user@host> show jps statistics message-handler message-flow
```

To view information about specific JPS message flows:

```
user@host> show jps statistics message-handler message-flow id id
```

Enter all or part of the message flow identifier to list all matching message flows.