

Configuring the Test Environment for PCMM Services

Configuring the settings for your test environment is optional. You can choose to enter the settings in the DSA SOAP Client window each time you use the Web client or to configure the default settings. If you choose the latter option, you can avoid repeatedly providing the same information each time you use the client.

- Configuring Settings for PCMM Services (SRC CLI) on page 1
- Verifying Settings for PCMM Services (SRC CLI) on page 1
- Deleting Settings for PCMM Services (SRC CLI) on page 1

Configuring Settings for PCMM Services (SRC CLI)

Use the following command to configure the testing environment for the PCMM Web service interface:

```
test dsa pcmm-service environment set <client-id client-id> <client-password  
  client-password> <subscriber-address subscriber-address> <subscriber-uri  
  subscriber-uri>
```

To configure the settings for the test environment:

1. Issue the `test dsa pcmm-service environment set` command.
2. (Optional) To specify the username that Dynamic Service Activator uses to authenticate this client, use the `client-id` option.
3. (Optional) To specify the password that Dynamic Service Activator uses to authenticate this client, use the `client-password` option.
4. (Optional) To specify the IP address of the subscriber, use the `subscriber-address` option.
5. (Optional) To specify the subscriber's uniform resource identifier (URI), use the `subscriber-uri` option.

Verifying Settings for PCMM Services (SRC CLI)

Use the following command to verify the settings for the PCMM Web service interface:

```
test dsa pcmm-service environment show
```

Use the following commands to verify specific settings:

```
test dsa pcmm-service environment show client-id  
test dsa pcmm-service environment show client-password  
test dsa pcmm-service environment show subscriber-address  
test dsa pcmm-service environment show subscriber-uri
```

Deleting Settings for PCMM Services (SRC CLI)

Use the following commands to delete the settings for the PCMM Web service interface:

```
test dsa pcmm-service environment clear
```

Use the following commands to delete specific settings:

```
test dsa pcmm-service environment clear client-id  
test dsa pcmm-service environment clear client-password  
test dsa pcmm-service environment clear subscriber-address  
test dsa pcmm-service environment clear subscriber-uri
```

- Related Topics**
- Testing the Web Application Gateway Client
 - Sample Data for Dynamic Service Activator
 - Configuring the Test Environment for Dynamic Service Activator Services
 - Running Methods for PCMM Services (SRC CLI)