

Configuring Profiler Database Preferences (NSM Procedure)

Data discovered by Profiler is stored in a database located on the NSM GUI server.

To configure Profiler database preferences:

1. Select **Tools > Preferences**.
2. Click **Profiler Settings**.
3. Configure database preferences using Table 1 on page 1.
4. Click **OK**.

Table 1: Profiler Database Preferences

Setting	Description
Purge Profiler Database if Size Exceeds	Default is 1000 MB.
Max Profiler Database Size After Purging	Default is 750 MB.
Profiler Query Timeout	Default is 120 seconds.
Hour of Day to Perform Database Optimization	Default is 00:00 GMT.

- Related Topics**
- [Configuring Profiler Options \(NSM Procedure\)](#)
 - [Displaying Profiler Database Information \(NSM Procedure\)](#)
 - [Using Profiler Viewer](#)

