

## Chapter 20

# Managing Operations

This chapter describes how to view the operations that have run using an existing schedule and to verify the next time they will run.

An operation appears in Monitor Operations when you run it using an existing schedule that you create using Settings > Schedule. An operation does not appear in Monitor Operations when you schedule an operation using the Now option.

All JUNOScope software users can view scheduled operations. Users with read-only privileges cannot delete operations.


This chapter includes the following topics:

- Viewing Scheduled Operations on page 212
- Deleting a Scheduled Operation on page 213

## Viewing Scheduled Operations

To view scheduled operations that have run and the next time they will run, do the following:

- In the JUNOScope main window, click Monitor > Operations. The Operations dialog box appears.



The Operations dialog box lists operations that are scheduled to be run by action name (a compound operation is labeled *run operation*), target device on which the operation ran (a compound operation name is displayed in this column), schedule name, when the operation is next scheduled to run, the last status, and an operation comment. If you click a link in the Last Status column, the Monitor > Status dialog box appears displaying the status of the operation.

If no scheduled operations appear in the Monitor—Operations dialog box, you have not created a schedule. For more information about creating a schedule, see “Setting Up Schedules” on page 103.

## Deleting a Scheduled Operation

---

You can delete a scheduled operation if it is not being used by an existing schedule. If an operation is being used in an existing schedule, you must first delete that schedule from Manage Operations.

To delete a scheduled operation, follow these steps:

1. In the JUNOScope main window, click Monitor > Operations. The Operations dialog box appears with a list of scheduled operations.
2. Select the check box for the scheduled operation that you want to delete.
3. Click Delete.

The scheduled operation is removed from the JUNOScope software database and will not run.

